

Network Speed Dome & PTZ Camera Web 3.0

User's Manual



ZHEJIANG DAHUA VISION TECHNOLOGY CO., LTD. V2.0.2



Foreword

General

The manual introduces the functions and operations of the web interface of the network speed dome and PTZ camera (hereinafter referred to as "the Device").

Safety Instructions

The following categorized signal words with defined meaning might appear in the manual.

Signal Words	Meaning
	Indicates a high potential hazard which, if not avoided, will result in death or serious injury.
	Indicates a medium or low potential hazard which, if not avoided, could result in slight or moderate injury.
	Indicates a potential risk which, if not avoided, could result in property damage, data loss, lower performance, or unpredictable result.
©—™ TIPS	Provides methods to help you solve a problem or save you time.
	Provides additional information as the emphasis and supplement to the text.

Revision History

Version	Revision Content	Release Time
	Added the note to provide	
V2.0.2	international calling codes for 4G	June 2020
	models.	
	Updated OSD info, TCP/IP and	
V2.0.1	smart plan, and delete life	April 2020
	statistics.	
	Added some functions of the	
V2.0.0	Baseline, and refine the whole	January 2020
	manual.	
V1.1.1	Updated some functions of the	September 2019
V 1. 1. I	Security Baseline.	
V1.0.0	First release.	May 2018

About the Manual

• The manual is for reference only. If there is inconsistency between the manual and the



actual product, the actual product shall prevail.

- We are not liable for any loss caused by the operations that do not comply with the manual.
- The manual would be updated according to the latest laws and regulations of related regions. For detailed information, see the paper manual, CD-ROM, QR code or our official website. If there is inconsistency between paper manual and the electronic version, the electronic version shall prevail.
- All the designs and software are subject to change without prior written notice. The product updates might cause some differences between the actual product and the manual. Please contact the customer service for the latest program and supplementary documentation.
- There still might be deviation in technical data, functions and operations description, or errors in print. If there is any doubt or dispute, please refer to our final explanation.
- Upgrade the reader software or try other mainstream reader software if the manual (in PDF format) cannot be opened.
- All trademarks, registered trademarks and the company names in the manual are the properties of their respective owners.
- Please visit our website, contact the supplier or customer service if there is any problem occurred when using the device.
- If there is any uncertainty or controversy, please refer to our final explanation.



Important Safeguards and Warnings

The manual will help you to use the Device properly. Read the manual carefully before using the Device, and keep it well for future reference.

Operation Requirements

- Avoid heavy stress, violent vibration, and water splash during transportation, storage, and installation. Complete package is necessary during the transportation. We assume no responsibility for any damage or problem caused by the incomplete package during the transportation.
- To avoid damage, protect the Device from falling down and heavy vibration. Arrange more than one person to move the Device when necessary.
- Buckle the safety hook before installing the Device if it is included.
- Keep the Device away from devices that generate electromagnetic field like televisions, radio transmitters, electromagnetic devices, electric machine, transformers, and speakers; otherwise image quality will be influenced.
- Keep the Device away from smoke, vapor, heat, and dust.
- Do not install the Device near heating furnace, spotlight, and other heat sources. If it is installed on ceiling, in kitchen or near boiler room, the Device temperature might rise.
- Do not dissemble the Device; otherwise it might cause dangers or device damage. Contact your local retailer or customer service center for internal setup or maintenance requirement.
- Make sure that there is no metal, or inflammable, explosive substance in the Device; otherwise it might cause fire, short-circuit, or other damage. Power off the Device and disconnect the power cord immediately if there is water or liquid falling into the Device. And contact your local retailer or customer service center. Avoid sea water or rain eroding the Device.
- Avoid aiming the lens at intense light source, including sunlight, and incandescent light; otherwise the lens might be damaged.
- Clean the enclosure with soft cloth. To remove the dirt, you can dip the soft cloth in proper detergent, wring the soft cloth out, and then dry the enclosure with soft cloth. Do not use gasoline, paint thinner, or other chemicals to clean the enclosure; otherwise it might result in enclosure transfiguration or paint flake. Read all the manuals included before using chemical cloth. Avoid long time touch between the plastic or rubber material and the enclosure; otherwise it might result in device damage and paint flake.



• It is recommended to use the Device with a lightning-proof device for better lightning-proof effect.

Requirements for Installation and Maintenance Personnel

- Have certificates or experiences related to installation and maintenance of the closed-circuit television (CCTV), and have certificates related to working at height.
- Have basic knowledge and installation skills of CCTV system.
- Have basic knowledge and operation technique for low-voltage wiring and low-voltage electronic circuit connection.
- Have the ability to read and understand the manual.

Requirements for Lifting the Device

- Use secure lifting appliances suitable for the installation place and the product installation mode.
- Make sure that the selected tools reach the installation height and have high safety performance.



- All installation and operations shall conform to local electrical safety regulations.
- The power source shall conform to the requirements of the Safety Extra Low Voltage (SELV) standard, and supply power with rated voltage which conforms to Limited Power Source requirement according to IEC60950-1. Note that the power supply requirement is subject to the device label.
- Use the power adapter recommended by the manufacturer.
- For the Device that supports laser, do not aim the laser directly at eyes. And keep a proper distance from the flammable to avoid fire.
- Do not connect several devices to one power adapter; otherwise it might result in overheat or fire if it exceeds the rated load.
- Make sure that the power is off when you connect the cables, install or uninstall the Device.
- Power off the Device and disconnect the power cord immediately if there is any smoke, disgusting smell, or noise from the Device. And contact your local retailer or customer service center.
- Contact your local retailer or customer service center if the Device is abnormal. Do not disassemble or repair the Device by yourself. We assume no responsibility for any problems caused by unauthorized modifications, disassembly or repair, incorrect installation or use, and overuse of certain components.



Table of Contents

Foreword	I
Important Safeguards and Warnings	III
1 Network Configuration	1
1.1 Network Connection	
1.2 Logging in to the Web Interface	1
1.2.1 Device Initialization	1
1.2.2 First-time Login	5
1.2.3 Device Login	6
1.2.4 Resetting Password	7
2 Live	10
2.1 Encoding Setting	10
2.2 Video Window Adjustment	11
2.3 System Menu	16
2.4 Video Window Functions	16
2.5 PTZ Configuration	19
2.6 PTZ Status	23
3 AI Live	25
3.1 AI Live Interface	25
3.1.1 Information Display Area of Detected Targets	25
3.1.2 Snapshot Display Area	
3.1.3 Statistics Area of the Detected Targets	
3.2 AI Live Settings	27
4 Playback	29
4.1 Video Playback	29
4.1.1 Video Play Function Bar	30
4.1.2 Recording Type	30
4.1.3 Auxiliary Functions	30
4.1.4 Video Playback File Search and Display Area	31
4.1.5 Video Clipping Area	34
4.1.6 Progress Bar Time Formats	34
4.2 Picture Playback	35
4.2.1 Picture Playing Functions	35
4.2.2 Picture Playback File Search and Display Area	36
4.2.3 Snapshot Types	37
5 Setting	38
5.1 Camera	38
5.1.1 Conditions Settings	38
5.1.2 Video	54
5.1.3 Audio	64
5.2 Network Settings	66
5.2.1 TCP/IP	66
5.2.2 Port	69



5.2.3 PPPoE	71
5.2.4 DDNS	71
5.2.5 SMTP (Email)	
5.2.6 UPnP	
5.2.7 SNMP	
5.2.8 Bonjour	
5.2.9 Multicast	
5.2.10 Auto Register	
5.2.11 Wi-Fi	
5.2.12 802.1x	
5.2.13 QoS	
5.2.14 4G	
5.2.15 Access Platform	
5.3 PTZ Settings	
5.3.1 Protocol	
5.3.2 Function	
5.4 Event Management	
5.4.1 Video Detection	
5.4.2 Smart Motion Detection	
5.4.3 Audio Detection	
5.4.4 Smart Plan	
5.4.5 IVS	
5.4.6 Face Recognition	
5.4.7 People Counting	
5.4.8 Heat Map	
5.4.9 Video Metadata	
5.4.10 Alarm	
5.4.11 Abnormality	
5.5 Storage	
5.5.1 Schedule	
5.5.2 Snapshot by Location	
5.5.3 Destination	
5.5.4 Record Control	
5.6 System Management	
5.6.1 Device Settings	
5.6.2 Account Settings	
5.6.3 Safety	
5.6.4 Peripheral	
5.6.5 Default	
5.6.6 Import/Export	
5.6.7 Auto Maintain	
5.6.8 Upgrade	
5.7 Information	
5.7.1 Version	
5.7.2 Log Information	171
5.7.3 Online User	




6 Alarm	174
7 Logout	176
Appendix 1 Cybersecurity Recommendations	177



1 Network Configuration

1.1 Network Connection

To view the web interface on your PC, connect the Device to the PC first. There are mainly two connection modes between the Device and PC. See Figure 1-1 and Figure 1-2. Figure 1-1 Direct connection by using a network cable



The models presented in the figures are for reference only, and the actual product shall prevail. All devices have the same IP address (192.168.1.108 by default) when they are delivered out of factory. To make the device get access to network smoothly, plan available IP segment reasonably according to practical network environment.

1.2 Logging in to the Web Interface

1.2.1 Device Initialization

For first-time use or after you have restored the Device to defaults, you need to initialize the Device by performing the following steps.



<u>Step 1</u> Open the browser, enter the IP address of the Device in the address bar, and then press the Enter button.

The **Country/Region Setting** interface is displayed. Set the **Country/Region**, **Language** and **Video Standard** as needed. See Figure 1-3.

Figure 1-3 Country/region setting interface

Country/Region Setting			
Country/Region	Australia	•	
Language	English	•	
Video Standard	PAL	•	
		Save	

<u>Step 2</u> Click **Save**, and the **Time Zone Setting** interface is displayed.

Configure time parameters. See Figure 1-4.

Figure 1-4 Time zone setting interface

Zone Setting	
Date Format	YYYY-MM-DD
Time Zone	(UTC+04:30) Kabul
Current Time	2019-02-27 🛅 13 : 51 : 36 Sync PC
It will be modified as	2019-02-27 10:21:36
	Next

Step 3 Click Next.

The **Device Initialization** interface is displayed. For the interface, see Figure 1-5. For the parameter description, see Table 1-1.



Figure 1-5 Device initialization

Device Initialization	
Username	admin
Password	•••••
Confirm Password	Strong
	Use a password that has 8 to 32 characters, it can be a combination of letter(s), number(s) and symbol(s) with at least two kinds of them.(please do not use special symbols like ' " ; : &)
Email Address	h To reset password, please input properly or update in time.
	Save

Table 1-1 Device initialization parameter description


Parameter	Description
Username	It is admin by default.
Password	The password should consist of 8 to 32 non-blank characters and contain at least two types of characters among upper case, lower case, number, and special characters (excluding ' "; : &). Set a high security password according to the prompt of password strength. Make sure that the new password is the same as the confirming password.
Confirm Password	Enter the confirming password that shall be the same as the password you entered.
Email Address	Set the email address which is used to reset password.

Step 4 Click Save.

The End-User License Agreement interface is displayed. See Figure 1-6.



Figure 1-6 End-user license agreement



<u>Step 5</u> Select I have read and agree to all terms check box, and then click Next.



The **P2P** interface is displayed. See Figure 1-7.

Figure 1-7 P2P interface

<u>Step 6</u> Scan the QR code on the interface, download the app, and then finish configurations according to the instructions on your mobile device. After that, click **Next**. The **Online Upgrade** interface is displayed. See Figure 1-8.



Figure 1-8 Online upgrade

Onlin	e Upgrade
×	Auto-check for updates Automatically notify me when updates are available. The system checks for updates daily.
	To inform you of the latest firmware upgrades for your device, we need to collect device info such as IP address, device name, firmware version, device SN, etc. All collected info is used only for the purposes of verifying device validity and pushing upgrade notifications.
	Next

- <u>Step 7</u> Select **Auto-check for updates** check box as needed. After the function is enabled, the Device will check for updates once a day automatically. There will be system notice if any update is available.
- <u>Step 8</u> Click **Next**, and the login interface is displayed. See Figure 1-9. Figure 1-9 Login interface

(a)hua	
Username:	
Password:	Forgot password
[Login Cancel

1.2.2 First-time Login

You need to download and install the plug-in for the first-time login.

- <u>Step 1</u> Open the browser, enter the IP address of the Device in the address bar, and then press the Enter button.
- <u>Step 2</u> Enter the username and password, and then click Login.


The web interface is displayed.

- If you enter the wrong password for 5 times, the account will be locked for 5 minutes. After the locked time, you can log in to the web interface again.



- You can set the number of allowed password attempts and locked time in "5.4.11.3 Illegal Access."
- <u>Step 3</u> Download and install the plug-in according to the on-screen instruction after logging in to the web interface. See Figure 1-10.

Figure 1-10 Installing the plug-in



<u>Step 4</u> After the plug-in is installed, the web interface will be refreshed automatically, and the video is displayed in **Live** interface. See Figure 1-11. Figure 1-11 Live interface



\square

The **Live** interface shown in the manual is for reference only, and the actual interface shall prevail.

1.2.3 Device Login

<u>Step 1</u> Open the browser, enter the IP address of the Device in the address bar, and then press the Enter key.

The Login interface is displayed. See Figure 1-12.



Figure 1-12 Device login



Step 2 Enter the username and password, and then click Login.

The web interface is displayed, and the video is displayed in **Live** interface.

- If you enter the wrong password for 5 times, the account will be locked for 5 minutes. After the locked time, you can log in to the web interface again.
- You can set the number of allowed password attempts and locked time. For details, see "5.4.11.3 Illegal Access."

1.2.4 Resetting Password

If you forget the password of the admin user, you can set the password through the provided email address.

Before resetting the password, you need to provide the email address in advance. For details,

see "1.2.1 Device Initialization" or "5.6.3.2 System Service."

<u>Step 1</u> Open the browser, enter the IP address of the Device in the address bar, and then press the Enter key.

The **Login** interface is displayed. See Figure 1-13.



Figure 1-13 Login



<u>Step 2</u> Click **Forgot password?**, and the **Prompt** interface is displayed. See Figure 1-14. Figure 1-14 Prompt

Prompt
In order to provide a secure password reset environment, we need to collect your e-mail address, device MAC address, device SN, etc.
All collected info is used only for the purposes of verifying device validity and sending a security code to you. Do you agree and want to continue
the operation?
OK Cancel

Step 3 Click **OK** to reset the password. The **Reset the password (1/2)** interface is displayed.

If you click **OK**, your email address, MAC address, device serial number, and other information might be collected.

rigule 1-15 Resetting the password (1)	1-15 Resetting the passwor	rd (1)	
--	----------------------------	--------	--

Reset the pas	sword(1/2)	
SN: 5	0.997	
QR code:	Note(For admin only): Option 1. Please download DMSS and then from More-Reset Device Password, scan the left QR code on the actual interface. Option 2. Please use an APP to scan the left QR code to get encryption strings. And then send the strings to support_rpwd@global.dahuatech.com.	
	The security code will be delivered to	
Security code:		
	Cancel Next	



<u>Step 4</u> Scan the QR code on the actual interface according to the instructions, and then enter the security code received in the mailbox.

Reset the password with the security code you received within 24 hours, otherwise the code will be invalid.

Step 5 Click Next.

The Reset the password (2/2) interface is displayed. See Figure 1-16.

Figure 1-16 Resetting the password (2)

Reset the password	(2/2)	
Username	admin	
Password		
	The minimum pass phrase length is 8 characters	
	Weak Middle Strong	
	Use a password that has 8 to 32 characters, it	
	can be a combination of letter(s), number(s) and	
	symbol(s) with at least two kinds of them.(please	
	do not use special symbols like ' " ; : &)	
Confirm Password		
	Cancel Save	
Stan 6 Sat than	accurate of the adminuteer again	

- <u>Step 6</u> Set the password of the admin user again.
 - Ш

The password should consist of 8 to 32 non-blank characters and contain at least two types of characters among upper case, lower case, number, and special characters (excluding ' "; : &). Set a high security password according to the prompt of password strength.

Step 7 Click Save.



2 Live

Click the **Live** tab, and the **Live** interface is displayed. See Figure 2-1. Figure 2-1 Live interface



For descriptions of function bars on the Live interface, see Table 2-1.

No.	Description
1	Encoding setting
2	Video window adjustment
3	System menu
4	Video window functions
5	PTZ configuration
6	PTZ status

2.1 Encoding Setting

Some devices do not support two sub streams.

For the encoding setting area, See Figure 2-2. For the parameter description, see Table 2-2. Figure 2-2 Encoding setting

	Main Stream	Sub Stream 1	Sub Stream 2	Protocol TCP	~
--	-------------	--------------	--------------	--------------	---



Table 2-2 Encoding setting parameter description			
Parameter	Description		
Main Stream	It has large bit stream value and image with high resolution, but requires large bandwidth. This option can be used for storage and monitoring.		
Sub Stream 1It has small bit stream value and smooth image, and r bandwidth. This option is normally used to replace main s bandwidth is not enough.			
Sub Stream 2	It has small bit stream value and smooth image, and requires little bandwidth. This option is normally used to replace main stream when bandwidth is not enough.		
Protocol	Select a protocol for video monitoring. The supported protocols include TCP (Transmission Control Protocol), UDP (User Datagram Protocol), and Multicast .		

2.2 Video Window Adjustment

For the video window adjustment bar, See Figure 2-3. For parameter description, see Table 2-3.




Figure 2-3 Video window adjustment

Table 2-3 Video window adjustment parameter description

No.	Parameter	Description
1	Image Adjustment	Click this button, and the Image Adjustment interface is displayed on the right side of the Live interface. You can adjust parameters such as brightness, contrast, hue, and saturation on the interface.
2	Original Size	Adjust the video image to original size.
3	Full Screen	Click this button, and the video is displayed in full screen. To exit full screen, double-click the screen or press the Esc button.
4	W:H	Adjust the video image to original ratio or a proper window.
5	Fluency	Click this button, and you can select Realtime , General , or Fluent . General is selected by default.
6	Rules Info	Click this button, and smart rules are displayed on the Live interface after the function is enabled. The function is



No.	Parameter	Description
		enabled by default.
7	PTZ	Click this button, and PTZ configurations are displayed on the Live interface after the function is enabled.
8	Face	Click this button, and face pictures are displayed on the screen. See Figure 2-8.
9	Video Metadata	Click this button, and information about motor vehicles, non-motor vehicles, and people is displayed on the screen in real time. See Figure 2-11.
10	Anti-aliasing	Click this button to enable anti-aliasing, and then aliasing can be avoided when video windows are small.
11	Panorama	Click this button, and a panorama window is displayed on the Live interface. You can perform operations such as positioning, calling presets, and setting tours.

Image Adjustment

For **Image Adjustment** interface, see Figure 2-4. For parameter description, see Table 2-4. Figure 2-4 Image Adjustment




Table 2-4 Image adjustment parameter description

Parameter	Description
`	Adjust the image brightness.
\bullet	Adjust the image contrast.
9	Adjust the image hue.
1	Adjust the image saturation.
Reset	Restore brightness, contrast, saturation and hue to default values.

Refresh



Only brightness, contrast, hue, and saturation of live view image on the web interface can be adjusted with this function. To adjust the brightness, contrast, hue, and saturation of the Device, you can go to **Setting > Camera > Conditions**.

Panorama

For the **Panorama** interface, see Figure 2-5.

Figure 2-5 Panorama interface



- You can perform positioning in this window by drawing a box with the left mouse button. The located area is displayed on the **Live** interface and enlarged.
- After you click **Refresh**, the Device rotates from 0 to 360 degrees horizontally and from 6 to 65 degrees vertically to obtain a new panoramic image.
- You can adjust the size of the panoramic image by dragging the screen ratio bar




Panorama Preset Tour

• You can click Preset to call a corresponding preset on the right side of the window. For the interface, see Figure 2-6. For how to set a preset, see "5.3.2.1 Preset."

Figure 2-6 Preset

You can click to call a corresponding tour on the right side of the window. For the interface, see Figure 2-7. For how to set a tour, see "5.3.2.2 Tour."





Face

For the **Face** interface, see Figure 2-8. Face recognition result is displayed on the left side, and the captured face picture and attributes are displayed on the right side.

Figure 2-8 Face



• Face recognition result display area: Displays the captured small face pictures, the corresponding face pictures in the database, and the similarities between them. After you click the picture, the attributes and details are displayed. See Figure 2-9.



Figure 2-9 Face recognition result display

MoreInfo			23
Alarm Info	Face Database: Similarity: 93 Time: 2019-10-17 12:04:20		
Attribute			
THE .	Age: Young	Gender: Male	
1000	Expression: Normal	Glasses: No	
	Mouth Mask: No	Beard: No	
Moreinfo			
6	Name:		
100	Date of Birth: Unknown	Gender: Unknown	
10	Type: Unknown	ID No.: Unknown	

• Face and attributes display zone: Displays the captured small face pictures and information such as gender, age, and expression. After you click the picture, the details are displayed. See Figure 2-10.

Figure 2-10 Face and attributes display

Moreinfo			×
Alarm Info	Time 2019-10-17 12:05:26		
Attribute	-		
Sec. 1	Age: Young	Gender: Female	
and the second	Expression: Normal	Glasses. General	
A	Mouth Mask: No	Beard: No	

Video Metadata

For the interface, see Figure 2-11. Motor vehicle information is displayed on the right side, and the information about human and non-motor vehicles is at the bottom of the interface. For more details, see "5.4.9 Video Metadata."







2.3 System Menu

To access an interface, click the corresponding tab on the system menu. For the system menu, see Figure 2-12.

Figure 2-12 System menu					
Live	Playback	Setting	Alarm	Logout	

2.4 Video Window Functions

For the video window function buttons, See Figure 2-13. For the parameter description, see Table 2-5.




Figure 2-13 Video window function buttons

Table 2-5 Video window function button description

No.	Parameter	Description	
1	Wiper Control	Click this button to select wiper operation.	
		Start: Click this button, and the wiper starts and waves	
		continuously.	
1		Stop: Click this button, and the wiper is turned off and stops	
		waving.	
		Once: Click this button, and the wiper starts and waves from	



No.	Parameter	Description		
		left to right for one time.		
		Click this button, right-click on the Live interface, and the		
		function menu is displayed. See Figure 2-14. You can add		
		information on the Live interface, and also manage added		
		comments.		
2	Mark	• Add Info: Select Add Info from the pop-up menu, and		
		enter the comment. For the interface, see Figure 2-15.		
		Managing comments: Select Info Management from		
		the pop-up menu to display, hide, or delete added		
		comments. For the interface, see Figure 2-16.		
		Click the button, draw a box with the mouse on the live view,		
3	Regional Focus	and then the Device will automatically focus on the area in		
		the box.		
		Click the button, and an alarm will be triggered. When an		
4	Relay-out	alarm is triggered, the icon turns red; and when an alarm is		
		canceled, the icon turns grey.		
		Click the button, and you can drag the live view by pressing		
5	Gesture Control	and holding the left mouse button to control PTZ; and you		
		can also zoom in or out through the mouse wheel.		
		• Click the button, and then select an area in the live view		
		to zoom in; right-click on the image to restore to the		
6	Digital Zoom	original status. In enlarged status, drag the image to		
		check other area.		
		• Click the button, and then scroll the mouse wheel in the		
		live view to zoom in or out.		
7	Spanshat	Click the button to capture one picture of the current image, and it will be saved to the live snapshot storage path set in		
1	Snapshot	"5.1.2.5 Path."		
		Click the button, and three pictures of the current image are		
		captured with one snapshot per second. These snapshots		
8	Triple Snapshot	will be saved to the live snapshot storage path set in "5.1.2.5		
		Path."		
		Click the button to record videos. The recording will be		
9	Record	saved to the live recording storage path set in "5.1.2.5		
		Path."		
		Click the button and select any area by dragging the left		
10	Manual Track	mouse button in the video window; the Device tracks objects		
		in this area intelligently.		
		Click the button to enable or disable audio output of the		
	Audio	monitoring stream.		
11				
		Before using the function, you need to enable the audio of		
		the corresponding stream in Setting > Camera > Audio		
		first.		
12	Talk	Click the button to enable or disable the two-way audio.		



Figure 2-14 Mark—menu




Figure 2-15 Mark—adding comments





Figure 2-16 Mark—managing comments



2.5 PTZ Configuration

You can control PTZ by using the **PTZ Control** panel or joystick. You can also set preset, scanning, and other functions in the **PTZ Function** area.

PTZ Control

Before using the **PTZ Control** panel, you need to set the PTZ protocol by selecting **Setting > PTZ > Protocol**.

For **PTZ Control** panel, See Figure 2-17. For parameter description, see Table 2-6.

Figure 2-17 PTZ control




Table 2-6 PTZ control parameter description

No.	Parameter	Description		
1	Direction buttons	There are 8 directions: Up, down, left, right, upper left, upper		
1	Direction buttons	right, lower left, and lower right.		
		Provides quick positioning function. Draw an box in the live		
2	Position	view with the mouse, and then the PTZ rotates to and		
		focuses on the selected area rapidly.		
3	Speed	The changing speed of PTZ direction. The higher the value,		
3	Speed	the faster the speed.		
4	Zoom/Focus/Iris	Click to increase the value, and click to to decrease the value.		

Joystick

You can drag the middle button to simulate joystick operations to control device rotation. For the operation interface, see Figure 2-18. Speed, zoom, focus, and iris configurations are the same as that of **PTZ Control** panel.



Figure 2-18 Joystick



PTZ Functions

The PTZ supports multiple functions. Select a function, click Start or Goto to start using the function, and then click stop to stop using the function. For the configuration interface, see Figure 2-19. For the supported functions and settings, see Table 2-7. Figure 2-19 PTZ function

PTZ Function	Menu	
Tour	~	
1	1~8	
Start	Stop	

Table 2-7 PTZ functions description

Parameter	Description
Scan	Select Scan from the list, enter a scan number, and then click Start . The PTZ starts scanning, and the default number is 1.
Preset	Select Preset from the list, enter a preset number, and then click Go to . The PTZ will rotate to the preset position.
Tour	Select Tour from the list, enter a tour number, and then click Start . The PTZ starts to tour.



Parameter	Description		
Pattern	Select Pattern from the list, enter a pattern number, and then click Start . The PTZ starts to pattern.		
Assistant	Reserved for special requirements.		
Pan	Select Pan from the list, and then click Start . The PTZ starts to pan.		
Go to	 Select Go to from the list, enter horizontal angle value, vertical angle value and zoom, and then click Go to. The Device will turn to the position you want. One unit of the horizontal angle value or vertical angle value you enter equals 0.1 degree. 		

Menu

For the menu interface, see Figure 2-20. For the parameter description, see Table 2-8. Figure 2-20 Menu interface



Table 2-8 Menu parameter description

Parameter	Description
Direction buttons	Click the up and down buttons to select parameters, and click the left and right buttons to select parameter values.
ОК	Confirmation button.
Open	Open the OSD menu.
Close	Close the OSD menu.

Click **Open** to open the OSD menu. The OSD menu is displayed on the live view. See Figure 2-21.



Figure 2-21 OSD menu



You can finish the following settings through the menu:

- Camera settings: See "5.1 Camera."
- PTZ settings: See "5.3 PTZ Settings."
- System management: See "5.6 System Management."

Ш

You can change the location of the OSD menu in "5.1.2.3 Overlay."

2.6 PTZ Status

On the **Live** interface, the PTZ status is displayed at the lower right corner. See Figure 2-22.

The function is available on select models.



When the PTZ lifespan is close to the threshold, a warning will be displayed on the **Live** interface. See Figure 2-23 and Figure 2-24.

Figure 2-23 Warning (1)





Figure 2-24 Warning (2)





3 AI Live

You can check the information of the detected human faces, human bodies, motor vehicles, and non-motor vehicles.

This function is available on select models.

3.1 AI Live Interface

For the **Al Live** interface, see Figure 3-1. For the layout description, see Table 3-1. Figure 3-1 Al live interface




Table 3-1 AI live interface description

No.	Function
1	Live view
2	Snapshot display area
3	Information display area of detected targets
4	Statistics area of the detected targets

3.1.1 Information Display Area of Detected Targets

Display the information of the captured targets in real time. See Figure 3-2.







3.1.2 Snapshot Display Area

Display the snapshots of the detected targets. See Figure 3-3. Click any snapshot to view the information of the detected target in information display area.

Figure 3-3 Snapshot display area



3.1.3 Statistics Area of the Detected Targets

Display the number of the captured target in real time. See Figure 3-4.

Figure 3-4 Statistics area of the detected targets



Table 3-2 Statistics area description of the detected targets

lcon	Detected Target	Description	
.	Face	Available detection items: Gender, age, expression,	
		glasses, mouth mask, and beard.	
ŤŤ	Human	Available detection items: Top, bottom, top color, bottom	
TT		color, bag, hat, and umbrella.	
II.	Non-motor vehicle	Available detection items: Vehicle type, vehicle body color,	
(UND		top, top color, occupancy, and hat.	
	Motor vehicle	Available detection items: License plate, vehicle body color,	
		vehicle type, vehicle logo, vehicle series, sunshield,	
		seatbelt, smoking, calling, ornament, and annual inspection	
		mark.	
		Up to 7 items can be selected at the same time for motor	
		vehicle detection.	
•	Settings	Click the button to select the detection items.	

3.2 AI Live Settings

Preparation

Select Setting > Event > Smart Plan, and then enable Face Detection, Face Recognition or Video Metadata. For the method to enable the function, see "5.4.4 Smart Plan.". For the operations, see "5.4.6 Face Recognition" or "5.4.9 Video Metadata."


Procedure

<u>Step 1</u> Click the **AI Live** tab. The **AI Live** interface is displayed. See Figure 3-5. The information display area of detected targets is on the right side; the snapshot display



area is on the bottom; the statistics area of the detected targets is on the lower right corner.

Figure 3-5 AI live interface



Step 2 Click

to set the detection items of the targets. See Figure 3-6.

Figure 3-6 Detection items selection interface

Face Detect	tion (Select m	nax 7 items.)	
Gender	Age	Express	Glasses
Mouth	Beard		
Human Dete	ection (Select	t max 7 items.))
Gender	Тор Туре	Bottom	Top Color
Bottom	Bag	Hat	Umbrella
Non-motor \	/obiclo Dotoc	tion (Select m	av 7 item
Non-motor			
Vehicle	Vehicle	Тор Туре	Top Color
Cycling	Hat		
Motor Vehic	le Detection	(Select max 7	items.)
Vehicle	Vehicle	License	Sunshield
Seatbelt	Smoke	Calling	Ornament
Inspecti			

Step 3 Click to complete the configuration.




4 Playback

You can watch the saved pictures and videos on the **Playback** interface.

Before using the function, you need to set the period, storage method, and record control of recording and snapshot first. For details, see "5.5 Storage."

Click the **Playback** tab, and the **Playback** interface is displayed. See Figure 4-1.


Figure 4-1 Playback interface



4.1 Video Playback

Select **dav** from the **File Type** list, and the video playback interface is displayed. See Figure 4-2. For parameter description, see Table 4-1.

Figure 4-2 Video playback



No.	Description
1	Video playing function bar
2	Progress bar



No.	Description
3	Recording types
4	Auxiliary functions
5	Video playback file search and display area
6	Video clipping area
7	Progress bar time formats

4.1.1 Video Play Function Bar

For the video playing function bar, see Figure 4-3. For the parameter description, see Table 4-2. Figure 4-3 Video playing function bar




No.	Parameter	Description				
1	Play	Play the video.				
2	Stop	Stop playing the video.				
3	Next Frame	Play the next frame.				
		frame.				
4	Slow	Slow down video playing.				
5	Fast	Speed up video playing.				
6	Sound	Mute or unmute the sound.				
7	Volume	Adjust the volume.				
8	Rules Info	Click this button, and smart rules will be displayed on the video playback interface if the smart rules are enabled.				

Table 4-2 Video play function bar description

4.1.2 Recording Type

Select a recording type, and then only files of the selected types will be displayed in the progress bar and file list. See Figure 4-4.



4.1.3 Auxiliary Functions

For the auxiliary functions, see Figure 4-5. For the parameter description, see Table 4-3.

Figure 4-5 Auxiliary functions



Table 4-3 Auxiliary functions parameter description

No.	Parameter	Description				
	Digital Zoom	• Click the button, and then select an area in the live view				
		to zoom in; right-click on the image to restore to the				
1		original status. In zoomed-in status, drag the image to				
1		check other areas.				
		• Click the button, and then scroll the mouse wheel in the				
		live view to zoom in or out.				
	Snapshot	Click the button, and then you can take snapshots of the				
2		video in playback, and save them in the playback snapshot				
		path set in "5.1.2.5 Path."				

4.1.4 Video Playback File Search and Display Area

There are videos and snapshots on days with blue shading. See Figure 4-6. For the parameter description, see Table 4-4.

File Type dav 💌							
Data	Src	S	D Ca	rd	_	-	
Jul		•	<	2	018	>	
Sun	Mon	Tue	Wen	Thu	Fri	Sat	
1	2	3	4	5	6	7	
8	9	10	11	12	13	14	
15	16	17	18	19	20	21	
22	23	24	25	26	27	28	
29	30	31					
1.0			8			- 1	

Figure 4-6 Playback file (1)



Table 4-4 Playback file parameter description (1)					
Parameter	Description				
File Type	• To play back a recording, select dav .				
гле туре	• To play back a picture, select jpg .				
Data Src	The SD Card is used by default.				
₽.	Click this button, and recordings or pictures of a certain type on specific dates can be downloaded in batch.				
	The function is available on select models.				
	File list. Click this button, and the recording files on the selected day will be displayed in the list.				

Download in Batches

Step 1 Click

ς.

The Batch Download interface is displayed. See Figure 4-7.

Batch Download × Туре All Videos -Start Time 2018-07-18 **00** : 00 : 00 End Time 2018-07-18 23 59 59 Search File Size: OKb • Туре dav Path C \Users\41590\WebDownload\PlaybackRecord Browse... Download

Figure 4-7 Batch download

Step 2 Configure parameters as needed. For the parameter description, see Table 4-5.

Parameter	Description			
	Select the event type that triggers video recording. All Videos ,			
Туре	General, Event, Alarm, Manual, and Snapshot are selectable. It is			
	All Videos by default.			
Start Time/EndTime	Select the start time and end time for video searching.			
File type	Select the video type. dav and mp4 are selectable. It is dav by default.			
Path	Click Browse , and set the saving path for video files. The default path			
Fau	is C:\Users\admin\WebDownload\PlaybackRecord.			
Stap 3. Click Search to search for the video files that mosts the requirements				

Table 4-5 Batch download parameters description

<u>Step 3</u> Click **Search** to search for the video files that meets the requirements.


<u>Step 4</u> Select the video, and click **Download**. The video files are downloaded and saved in the saving path.



You can select multiple files to download them.


Displaying File List

- <u>Step 1</u> Click a day with blue shading, and recording file progress bar with different colors is displayed on the time axis.
 - Green: Represents general videos.
 - Yellow: Represents motion detection videos.
 - Red: Represents alarm videos.
 - Blue: Represents manually recorded videos.
- <u>Step 2</u> Click anywhere on the progress bar, and the video will be played from that time. For the progress bar, see Figure 4-8.



- Step 3 Click , and videos recorded on the selected day will be displayed in a list.
- <u>Step 4</u> For the playback file list, see Figure 4-9. For the parameter description, see Table 4-6. To play back a file in the list, double-click the file.

Figure 4-9 Playback file (2)





Parameter	Description			
0	Search all the recorded files from the start time to the end time on the			
5	selected date.			
Download	There are two entiones day and mn4			
Format	There are two options: dav and mp4 .			
	Click the download button, and the files will be saved to the storage path			
•	set in "5.1.2.5 Path."			
V				
	Downloading and playing video at the same time is not supported.			
+	Click the button to go back to the calendar interface.			

Table 4-6 Playback file parameter description (2)

4.1.5 Video Clipping Area

You can clip the videos in this area. See Figure 4-10.

Figure 4-10 Video clipping



- <u>Step 1</u> Click the time axis to select the start time for video clipping. The time must be within the progress bar range.
- <u>Step 2</u> Hover over <u>Step 2</u>, and then **Select start time** is displayed.
- Step 3 Click to set the start time for video clipping.
- <u>Step 4</u> Click the time axis to select the end time for video clipping. The time must be within the progress bar range.
- Step 5 Hover over **L**, and then **Select end time** is displayed.
- Step 6 Click do set the end time for video clipping.
- Step 7 Click Mean Step 7 Click Step 3 Click Step 3 Step 3 Click Step 3 S

4.1.6 Progress Bar Time Formats

For the progress bar time format, see Figure 4-11. For the parameter description, see Table 4-7.

Figure 4-11 Progress bar time formats

()1hr ()30min O24hr O2hr



Parameter	Description				
O 24hr	Click the button, and then the progress bar displays the recordings in				
G 24fir	24-hour mode.				
O 2hr	Click the button, and then the video within the selected 2-hour period is				
Gzm	displayed.				
O 1hr	Click the button, and then the video within the selected 1-hour period is				
Gim	displayed.				
O 30min	Click the button, and then the video within the selected 30-minute period is				
Gaomin	displayed.				

Table 4-7 Progress bar time format description

4.2 Picture Playback

Select **jpg** from the **File Type** list. For the picture playback interface, see Figure 4-12. For the parameter description, see Table 4-8.

Figure 4-12 Picture playback





Table 4-8 Picture playback parameter description

No.	Description
1	Picture playing functions
2	Snapshot types
3	Picture playback file search and display area

4.2.1 Picture Playing Functions

For the picture playing buttons, see Figure 4-13.

Figure 4-13 Picture playing buttons





•

To pause the picture play, click 🔟 .

4.2.2 Picture Playback File Search and Display Area

For the playback file interface, see Figure 4-14 and Figure 4-15. For the description of buttons on the interface, see Table 4-9.

Figure 4-14 Playback file (1)								
	File Type jpg							
	Data Src SD Card						•	
	<	12			2013		>	
	Sun	Mon	Tue	Wed	Thu	Fri 🖇	Sat	
	1	2	3	4	5	6	7	
	8	9	10	11	12	13	14	
	15	16	17	18	19	20	21	
	22	23	24	25	26	27	28	
	29	30	31					
				E				
I			_		_			

Table 4-9 Button description

Parameter	Description
File Type	Select jpg from the File Type list, and the picture will be played if any.
Data Src	The SD Card is used by default.
	File list. Click this button, and the recording files on the selected day will be displayed in the list.



Figure 4-15 Playback file (2)

	,		(-/
00	: 00 : 00 -	23 : 5	9 : 59	٥
	Start Time	File Ty	ре	
	13:03:40		•	
2	13:03:41		•	
	13:03:42		•	
4	13:03:43		•	
	13:03:44		•	
	13:03:45		•	
	13:04:42		•	
8	13:04:43		•	
	13:04:44		•	
10	13:04:45		•	
11	13:04:46		•	
12	13:04:47		•	
13	13:04:48		•	
ŀ	◀ ◀ 1/8 ▶	► ► <mark>1</mark>	- R	
				_
		,		
		(


- Step 1 Click , and the snapshots on a selected day will be displayed in a list.
- <u>Step 2</u> To play back a snapshot, double-click the corresponding file. For the parameter description, see Table 4-10.

Table 4-10 Playback file	parameter description
--------------------------	-----------------------

Parameter	Description
٩	Search all the snapshots from the start time to the end time on the
<u>u</u>	selected date.
•	Click the button to download the snapshot to local storage.
+	Click the button to go back to the calendar interface.

4.2.3 Snapshot Types

After you select a snapshot type, only the files of the selected type are displayed in the file list. For snapshot types, See Figure 4-16.





5 Setting

5.1 Camera

5.1.1 Conditions Settings

This section describes how to set camera attributes and manage profiles.

5.1.1.1 Conditions

Picture

Set camera attributes and picture parameters to achieve the best display effect. <u>Step 1</u> Select **Setting > Camera > Conditions > Conditions > Picture**.

The **Picture** interface is displayed. See Figure 5-1.

Figure 5-1 Picture interface

Conditions Profil	e Management				
			Profile Day		~
		▶ Picture	Style Standar	d	~
A Levent		Exposure	Brightness	-0-	+ 50
inter inter	A A A A A A A A A A A A A A A A A A A	Backlight	Contrast 🖃	-0-	
A BARR		▶ WB	Saturation	-0-	+ 50
		Day & Night	Chroma CNT	-0-	+ 50
a constant	and the second	Focus & Zoom	Sharpness 🖃	-0-	+ 50
		IR Light	Sharpness CNT	-0-	+ 50
		Defog	Gamma 🔄	-0-	+ 50
			Flip 0°		~
			EIS O On	• Off	
3			Picture Freeze 🔘 On	• Off	
	Refresh Save				
Speed 5	 Zoom (+) Focus (+) Iris (+) 				

<u>Step 2</u> Configure parameters as needed. For parameter description, see Table 5-1.



_	Table 5-1 Picture setting parameter description
Parameter	Description
Profile	There are three options: General, Day, and Night. You can view the
	configurations and the effect of the selected mode. Day is selected by default.
Style	Set the image display style. There are three options: Soft , Standard , and
	Vivid. Standard is selected by default.
Brightness	Set the overall image brightness. The larger the value is, the brighter the image
5	will be. The value ranges from 0 to 100.
Contrast	Set the image contrast. The larger the value is, the greater the contrast will be.
	The value ranges from 0 to 100.
Saturation	Set the intensity of colors. The larger the value is, the brighter the colors will
	be. The value ranges from 0 to 100.
	The larger the value, the higher suppression on image colors. The value
Chroma	ranges from 0 to 100.
CNT	
	This parameter takes effect only when the Device is in the environment with
	low luminance.
	Set the sharpness of picture edges. The larger the value is, the more obvious
	the edge will be. The value ranges from 0 to 100.
Sharpness	
	If the value is too large, there might be image noise. Set the value according to
	the actual condition.
	The larger the value is , the stronger the sharpness CNT will be. The value
Sharpness	ranges from 0 to 100.
CNT	
	This parameter takes effect only when the Device is in the environment with
	low luminance.
	Change image brightness through non-linear tuning to expand the dynamic
Gamma	display range of images. The larger the value is, the brighter the image will be.
	The value ranges from 0 to 100.
	Monitoring videos can be flipped over. There are two options.
Flip	• 0 °: The monitoring video is normally displayed. It is 0 ° by default.
	• 180° : The monitoring video is flipped over.
	Electronic image stabilization (EIS) is used to effectively solve the problem of
	image shaking during use, thus presenting clearer images. It is Off by default.
EIS	This function is available on select models.
EIS	• This parameter takes effect only when the Device is in the environment
	with low luminance.
	• Optical image stabilization and electronic image stabilization cannot be
	enabled at the same time.
Picture	After you select On , the image at the called preset is displayed directly if you
Freeze	call a preset or tour, and no images during the rotation of the Device are
110020	displayed.

Table 5-1 Picture setting parameter description

Step 3 Click Save.




Exposure


You can control the amount of light per unit area reaching the electronic image sensor by adjusting parameters on the **Exposure** interface.

<u>Step 1</u> Select Setting > Camera > Conditions > Conditions > Exposure.

The **Exposure** interface is displayed. See Figure 5-2 to Figure 5-6.

Figure 5-2 Exposure—auto mode





		Profile	Day	~
	 Picture Exposure Backlight WB 		Aperture Priority 10 ~ 50	✓ ✓ (0~100) (1) 50
	 Day & Night Focus & Zoom IR Light 	AE Recovery	15Min. ● On ○ Off	× 50
D.D.C.	✤ Defog	3D NR Grade	• On O Off	
Default Refresh Save				
Speed $5 \checkmark$ Zoom $(+)$ (-) Zoom $(+)(-)$ Focus $(+)(-)$ Iris $(+)$				



Figure 5-4 Exposure—shutter priority mode




Figure 5-5 Exposure—gain priority mode

			Profile	Day		~
		Picture	Anti-flicker	Outd	oor	~
12-	A STATE OF AND AND A STATE AND	 Exposure 	Mode	Gain	Priority	~
	The second state and the second	Backlight	Gain	0	~ 50	(0~100)
T TO	AND A CONTRACT OF	▶ WB	Exposure Comp	0-	-0-	+ 50
		Day & Night	AE Recovery	15Mi	n.	~
ter.		Focus & Zoom	2D NR	• •	n 🔿 Off	
		IR Light	Grade	E -	0	+ 50
	S Das	Defog	3D NR	• •	n 🔿 Off	
			Grade	Ξ-	0	÷ 50
			Advanced NR	0 0	n Off	
Default	Refresh Save					
8	← Zoom (+) ← Focus (+)					
1						



Figure 5-6 Exposure—manual mode

Conditions	Profile Management				
			Profile	Day	~
Belak t	NUM BUT IN ANT THE DATE OF	▶ Picture	Anti-flicker	Outdoor	~
12-	A LAND THE REAL PROPERTY AND A LONG THE REAL A	▶ Exposure	Mode	Manual	~
	The second secon	 Backlight 	Shutter	1/25	~
- <u>1</u>		▶ WB	Gain	0 ~ 50	(0~100)
		Day & Night	Iris	10 ~ 50	(0~100)
		Focus & Zoom	AE Recovery	15Min.	~
		IR Light	2D NR	• On O Off	
	400	▶ Defog	Grade	⊡——0-	+ 50
			3D NR	On O Off	
			Grade	E-0-	+ 50
1			Advanced NR	🔿 On 💿 Off	
Default	Refresh Save				
Speed 5	$\begin{array}{c} \hline \\ \hline $				

Step 2 C	Configure para	ameters as needed	. For parameter	description, s	ee Table 5-2.
----------	----------------	-------------------	-----------------	----------------	---------------

Parameter	Description
Anti-flicker	 You can select 50Hz, 60Hz, or Outdoor from the list. 50Hz: When the alternating current is 50Hz, the exposure is automatically adjusted to make sure that there are no stripes on images. 60Hz: When the alternating current is 60Hz, the exposure is automatically adjusted to make sure that there are no stripes on images. Outdoor: You can switch the modes to achieve the effect you want.
Mode	 Set the exposure modes. You can select Auto, Manual, Aperture Priority, Shutter Priority, Gain Priority. The Auto mode is selected by default. Auto: Exposure is automatically adjusted according to scene brightness if the overall brightness of images is in the normal exposure range. Manual: You can adjust the Gain, Shutter, and Iris value manually. Aperture Priority: You can set the iris to a fixed value, and the Device adjusts shutter value then. If the image brightness is not enough and the shutter value has reached upper or lower limit, the system adjusts gain value automatically to ensure the image is at ideal brightness. Shutter Priority: You can customize the shutter range. The Device automatically adjusts the aperture and gain according to the scene brightness. Gain Priority: Gain value and exposure compensation value can be adjusted manually.



Parameter	Description	
Gain	You can set the exposure gain. The value ranges from 0 to 100.	
Obutton	You can adjust the exposure time of the Device. The larger the shutter	
Shutter	value, the brighter the image.	
Iris	You can set the Device luminous flux. The larger the iris value, the brighter	
IIIS	the image.	
Exposure	You can set the exposure compensation value. The value ranges from 0 to	
Comp	100.	
	Automatic exposure is an automated digital camera system that adjusts the	
	aperture and shutter speed, based on the external lighting conditions for	
AE Recovery	images and videos. If you have selected an AE Recovery time, the	
	exposure mode will be restored to the previous mode after you adjusted the	
	Iris value. There are five options: Off, 5Min, 15Min, 1Hour, and 2Hour.	
	2D noise reduction is the process of removing noise from a signal. The	
2D NR	higher the grade is, the less the noise will be, and images appear to be	
	blurrier.	
	3D noise reduction is the process of removing noise from a signal. The	
3D NR	higher the grade is, the less the noise will be, and images appear to be	
	blurrier.	
Grade	Noise reduction grade. The value ranges from 0 to 100. The larger the	
Glade	value is, the less the noise will be.	
	Realize noise suppression effect through 3D and 2D video filtering method.	
Advanced NR		
	The function is available on select models.	

Backlight

The backlight function cannot be configured if defog function is enabled. There will be a prompt on the interface.


You can use this function to adjust the backlight compensation mode of the monitoring screen.

<u>Step 1</u> Select Setting > Camera > Conditions > Conditions > Backlight.

The **Backlight** interface is displayed. See Figure 5-7.



Figure 5-7 Backlight settings



<u>Step 2</u> Select a backlight mode from the list.

There are 4 options: Off, BLC, HLC, and WDR.

- Off: Backlight is disabled.
- BLC: Backlight compensation corrects regions with extremely high or low levels of light to maintain a normal and usable level of light for the object in focus.
- WDR: When in WDR (Wide Dynamic Range) mode, the Device constrains over bright areas and compensates dark areas to improve the image clarity.
- HLC: Highlight compensation dims strong light, so that the Device can capture details of faces and license plates in extreme light conditions. It is applicable to the entrance and exit of toll stations or parking lots.

Step 3 Click Save.

If you select **Off**, other backlight mode configurations will not be effective.

WB


In this mode, you can make a white object displaying itself clearly on the video image in all environments.

<u>Step 1</u> Select Setting > Camera > Conditions > WB.

The **WB** interface is displayed. See Figure 5-8.



Figure 5-8 WB settings



Step 2 Select WB mode from the list.

You can select from Auto, Indoor, Outdoor, ATW, Manual, Sodium Lamp, Natural, and Street Lamp. Auto is selected by default.

Step 3 Click Save.

Day & Night

Defog function cannot be configured if **Day & Night** function is enabled. There will be a prompt on the interface.


This function allows you to switch between the color mode and the black & white mode, ensuring clear monitoring screen in a dim environment.

<u>Step 1</u> Select Setting > Camera > Conditions > Conditions > Day & Night.

The Day & Night interface is displayed. See Figure 5-9.



Figure 5-9 Day & night settings



Step 2	Configure parameters as needed	. For parameter description	see Table 5-3.
0.00 2			

Parameter	Description	
	There are two options: Electrical and ICR. ICR is selected by default.	
Туре	• ICR: IR filter is used for day & night switch.	
	• Electrical: Image processing method is used for day & night switch.	
	Select a mode from the list (Your selection is independent from the profile).	
	Auto is selected by default.	
Mode	Color: The Device only outputs color images.	
WOUE	• Auto: The Device outputs color images or black-and-white images	
	according to ambient conditions.	
	• B/W : The Device only outputs black-and-white images.	
	Adjust the sensitivity to switch between different modes. There are three	
Sensitivity	options: Low, Middle, and High.	
	You can set sensitivity only when Day & Night mode is set to Auto.	
	Adjust the delay time to switch between different modes. The value ranges	
	from 2 s to 10 s.	
Delay		
	You can set Delay only when Day & Night mode is set to Auto .	

Table 5-3 Day & night parameter description


Step 3 Click Save.

Focus & Zoom

Digital zoom refers to capturing a part of the image to magnify it. The higher the magnification is, the blurrier the images will become.



<u>Step 1</u> Select Setting > Camera > Conditions > Conditions > Focus & Zoom. The Focus & Zoom interface is displayed. See Figure 5-10. Figure 5-10 Focus & zoom settings



Step 2 Configure each parameter as need	ded. See Table 5-4.
---	---------------------

Table 5-4 Focus & zoom parameter description
--

Parameter	Description	
Digital Zoom	Select On or Off to enable or disable digital zoom. Off is selected by	
	default.	
Zoom Speed	The larger the value is, the faster the Device zooms.	
	Select the focus triggering mode. There are three options: Semi Auto,	
	Auto, and Manual. Semi Auto is selected by default.	
	• Semi Auto: The Device focuses automatically when zoom or ICR	
Mada	switch is detected.	
Mode	• Auto: The Device focuses automatically when scene changes, zoom,	
	or ICR switch are detected.	
	• Manual: The Device cannot focus automatically. You need to adjust	
	the focus manually.	
	You can select the shortest focus distance, which means the Device will	
Focus Limit	focus on objects farther than the shortest focus distance. If you select	
	Auto, the Device will select an appropriate shortest distance according to	
	the zoom value.	
	Sensitivity is the capacity of resisting interference of the Device when	
Sensitivity	focusing. The smaller the value is, the more capable the Device can resist	
	interference when focusing.	
PFA	If you enable this function, the image is relatively clear during zoom. If you	
	disable this function, the speed is relatively high during zoom.	



Parameter	Description
Lens	Click this button, and the lens will be initialized automatically. The lens will
Initialization	be extended to calibrate the zoom and focus.

IR Light

Common illuminators are classified into infrared IR lights, white lights, and laser lights. Different device models support different types of illuminators, and have different configuration interfaces. The actual interface shall prevail. This section describes how to configure these light types.

Infrared IR Light/White Light

These are the conditions for using infrared IR light and white light.

- When the day & night mode is set to **B/W**, the monitoring screen is black and white. In this case, infrared IR light is used.
- When the day & night mode is set to **Color**, the monitoring screen is colored. In this case, white light is used.
- When the day & night mode is set to **Auto**, the monitoring screen color changes with the ambient light condition, and the illuminator varies with the monitoring screen. In **B/W** mode, the infrared IR light is turned on; in **Color** mode, the white light is turned on.


• Some models are equipped with photoresistor that can turn on different types of illuminators based on the ambient brightness.

Perform the following steps to set illuminators.


Step 1 Select Setting > Camera > Conditions > Conditions > IR Light.


The **IR Light** interface is displayed. See Figure 5-11.


Figure 5-11 IR light settings—ZoomPrio












		Profile Day	~
Motor Vehicle-2291 Non-motor vehicle 2433 Septe 200 Sim Fish Treaser("Treading") Treaser("Treaser("Treading") Treaser(""Treaser("Treaser("Treaser("Treaser("Treaser("Treaser("Treaser("Treaser("Treaser("Treaser("Treaser(""Treaser(""Treaser(""Treaser(""Treaser(""Treaser(""Treaser(""Treaser(""Treaser(""Treaser("	 Picture Exposure Backlight WB Day & Night Focus & Zoom IR Light Defog 	Mode Manual	+ 50 + 0
Default Refresh Save			



Figure 5-14 IR light setting-timing



		Profile Day	~
or Vehicle-2299 emotor Vehicle-2435 pile 2000	 Picture Exposure Backlight WB Day & Night Focus & Zoom IR Light Defog 	Mode Off	~
Default Refresh Save			



Parameter	Description	
	There are 5 options: Manual, SmartIR, ZoomPrio, Timing, and Off.	
Mode	• ZoomPrio: The system adjusts the IR light brightness automatically	
Mode	according to the zoom times.	
	• SmartIR: The system controls the IR light intensity according to actual	

Table 5-5 IR light parameter description



Parameter Description		
	conditions.	
	Manual: Set IR light brightness manually.	
	• Timing : Enable different light types in different time periods according	
	to actual condition.	
	Off: Turn off the IR light.	
 Some models do not support SmartIR, Manual, Timing, or Off In ZoomPrio mode, IR light and white light are supported, and 		
	• In Timing mode, you can set four periods with different light types.	
	Only infrared IR light supports the SmartIR mode.	
	• The IR light is turned off for cameras with low power consumption by	
	default. Turn on the IR light if necessary.	
Light Type	You can select IR Light or White Light.	
Correction	Compensate for the brightness of the IR light. The value ranges from 0 to	
Correction	100.	
Near Light	Set the brightness of the near light. The value ranges from 0 to 100.	
Far Light	Set the brightness of the far light. The value ranges from 0 to 100.	


Laser Light

Laser light makes compensation for the ambient environment when it is used for long-distance monitoring.

<u>Step 1</u> Select Setting > Camera > Conditions > Conditions > IR Light.

The IR Light interface is displayed. See Figure 5-16.

Figure 5-16 Laser light settings



<u>Step 2</u> Configure parameter as needed. Refer to Table 4-6 for more details.



	Table 5-6 Laser light setting parameter description		
Parameter	Description		
	Select the laser light mode from ZoomPrio and Manual . It is ZoomPrio by default.		
Mode	• ZoomPrio : The Device can automatically adjust laser light brightness according to the zoom times.		
	 Manual: Manually set laser light brightness and angle value. 		
Laser	Set the intensity of the laser light. The value ranges from 0 to 100.		
Intensity	Set the intensity of the laser light. The value langes from 0 to 100.		
Laser Angle	Set the angle value from 0 to 100.		
Cham 2. Olials Car			

Defog

The defog function cannot be configured if backlight function is enabled. There will be a prompt on the interface.

Image quality drops if the Device is installed in foggy or hazy environment. You can enable defog to improve image quality.

<u>Step 1</u> Select Setting > Camera > Conditions > Conditions > Defog.


The **Defog** interface is displayed. See Figure 5-17 and Figure 5-18.

Figure 5-17 Defog settings—manual

		Profile	Day	~
P 276.013.8.40 Image: Constrained of the second se Second second sec	 Picture Exposure Backlight WB Day & Night Focus & Zoom IR Light Detog 	Intensity	Manual Medium O On Off	V V
Speed 5 V Zoom (+)				



Figure 5-18 Defog settings—auto



<u>Step 2</u> Configure parameters as needed. For parameter description, see Table 5-7.

Table 5-7 Defog parameter description

Parameter	Description
	Select the defog mode of the Device. You can select Auto, Manual, or
	Off. It is Off by default.
Mode	
Wouc	For the Device that supports optical defog, in Auto mode, optical defog
	and electronic defog switch automatically according to the algorithm.
	And in Off mode, electronic defog is enabled by default.
Intensity	Set the defog intensity of the Device. You can select from Low, Medium,
Intensity	or High .
Defer	Only the Device that supports optical defog has this parameter.
Defog Enhancement	In Manual mode, if you enable this function, both optical defog and
	electronic defog are enabled. (You need to enable Auto mode for Day &
	Night to use the function.)

Step 3 Click Save.

5.1.1.2 Profile Management

<u>Step 1</u> Select Setting > Camera > Conditions > Profile Management. The Profile Management interface is displayed.

<u>Step 2</u> Select the profile management mode.

There are three options: General, Full Time and Schedule.

• If you select General, monitoring is based on the general configuration of the Device. See Figure 5-19.



Figure 5-19 Profile management-general

Conditions Pro	file Management		
Profile Management	General O Full	Time 🔘 Schedul	e
	Default	Refresh	Save

 If you select Full Time, Day and Night are selectable, and the corresponding camera property profile is day or night. See Figure 5-20.

Figure 5-20 Profile management—full time

Conditions Pro	ofile Management
Profile Management	○ General ● Full Time ○ Schedule
Always Enable	Day
	Default Refresh Save

 If you select Schedule, you can select one period for day configuration and another period for night configuration. For the configuration interface, see Figure 5-21. For example, you can set the day-time configuration from 6:00 to 18:00, and set the night-time configuration from 18:00 to 6:00 on the next day.

Figure 5-21 Profile management—schedule

Conditions Pro	ofile Managem	ent					
Profile Management	⊖ General ⊖	Full Time 💿 S	chedule				
Period setting	0:00	4:00	8:00	12:00	16:00	20:00	24:00
		4.00 Night	8.00	12.00	10.00	20.00	24.00
	Default	Refresh	Sav	/e			

Step 3 Click Save.

5.1.2 Video

You can set the video stream, snapshot stream, video overlay, ROI, and storage path of the Device.

5.1.2.1 Video Stream

This section describes how to set the video stream for the monitoring screen.

```
<u>Step 1</u> Select Setting > Camera > Video > Video.
```

The Video interface is displayed. See Figure 5-22.



Figure 5-22 Video stream settings

Aain Stream					Sub Stream			
					C Enable	Sub Stream 1	~	
Encode Mode	H 264H	¥			Encode Mode	H 264H	~	
Smart Codec	Off	v			Resolution	704*576(D1)	~	
Resolution	1920*1080(1080P)	¥			Frame Rate(FPS)	25	~	
Frame Rate(FPS)	25	¥			Bit Rate Type	CBR	~	
Bit Rate Type	CBR	×			Reference Bit Rate	256-2304Kb/S		
Reference Bit Rate	1792-8192Kb/S				Bit Rate	1024	✓ (Kh/S)	
Bit Rate	4096	Y	(Kb/S)		I Frame Interval	50	(25~150)	
I Frame Interval	50		(25-150)		SVC	1(off)	¥	
SVC	1(off)	Y						
Watermark Settings								
Watermark Characte	DigitalCCTV							
Watermark Characte	r DigitalCCTV							

- The stream configuration interfaces might vary depending on devices, and the actual interface shall prevail.
- The default bit rate of different devices might vary, and the actual product shall prevail.

<u>Step 2</u> Configure parameters as needed. For parameter description, see Table 5-8.

Parameter	Description		
Enable	You can select the check box to enable sub stream. The sub stream is		
Ellable	enabled by default.		
Encode Mode	You can select H.264, H.264H, H.264B, H.265, MJPEG, MPEG4, or		
Encode Mode	SVAC.		
	Enable Smart Codec to improve video compressibility and save storage		
	space.		
Smart Codec			
	After Smart Codec is enabled, the Device does not support the third stream,		
	ROI, smart event, and other functions. The actual interface shall prevail.		
Resolution	Multiple resolution types are available for you to choose, and each type		
Resolution	corresponds to a unique recommended stream value.		
Frame Rate	PAL: 1–25 frames/s or 1–50 frames/s. The frame rate changes with the		
(FPS)	resolution.		
	There are two options: CBR (constant bit rate) and VBR (variable bit		
	rate).		
Bit Rate Type	• Picture quality can be set only in VBR mode, and cannot be set in		
	CBR mode.		
	• In MJPEG encode mode, CBR is the only option for Bit Rate Type.		
Reference Bit	The recommended bit rate range is based on the resolution and frame		
Rate	rate.		
Bit Rate	It is the upper limit of stream in VBR. In CBR, the value is fixed.		
	The number of P frames between two I frames. The range varies with the		
I Frame Interval	frame rate, and the maximum value is 150. It is recommended to set the		
	interval twice the frame rate.		

Table 5-8 Video stream parameter description



Parameter	Description
SVC	Layered encoding can be done for FPS. SVC is a scalable encoding
	method on time domain. It is 1 by default, which means no layered
	coding. You can set 2, 3 or 4 layered encoding.
Watermark	You can varify the watermark to sheek if the video has been tempored
Settings	You can verify the watermark to check if the video has been tampered.
	You can verify the watermark to check if the video has been tampered.
	Select Watermark Settings check box to enable Watermark Character.
Matarmark	The watermark character is DigitalCCTV by default, and you can modify
Watermark Character	it.
	Watermark character consists of up to 128 characters from letters, standard
	symbols, spaces, and special characters.

5.1.2.2 Snapshot

This section describes how to set streams for snapshots.

<u>Step 1</u> Select Setting > Camera > Video > Snapshot.

The **Snapshot** interface is displayed. See Figure 5-23.

Figure 5-23 Snapshot stream settings

Video	Snapshot	Overlay	ROI	Path	
Snapshot Type	General	~			
Image Size	1080P (1920*1080)				
Quality	5	~			
Interval	15	~			
	Default	Refresh	Save		

<u>Step 2</u> Configure parameters as needed. For parameter description, see Table 5-9.

Parameter	Description
	You can select General or Event .
	• General refers to capturing pictures within the time range set in the
	schedule. For details, see "5.5.1 Schedule."
Snapshot Type	• Event means capturing pictures when motion detection, video
	tampering, or local alarms are triggered. For how to enable
	snapshots for motion detection, video tampering, or local alarms,
	see "5.4 Event Management."
Imaga Siza	It is the same as the resolution of the selected snapshot main stream,
Image Size	and cannot be modified on this interface.
Quality	You can set the snapshot quality from 1 to 6 levels. Level 1 is the lowest
Quality	level, and level 6 is the highest level.
Interval	Set the snapshot frequency. You can select from 1 s through 7 s or
Interval	Customized.

Table 5-9 Snapshot stream parameter description



5.1.2.3 Overlay

This section describes how to set the overlay information on the monitoring screen.

<u>Step 1</u> Select Setting > Camera > Video > Overlay.

The **Overlay** interface is displayed.

<u>Step 2</u> Configure overlay information as needed. For the configuration interfaces, see the following figures. For the parameter description, see Table 5-10.

Figure 5-24 Overlay settings—privacy masking




Figure 5-25 Overlay settings—channel title









Figure 5-27 Overlay settings—OSD info








Figure 5-29 Overlay settings—picture overlay






Figure 5-30 Overlay settings—abnormal




Figure 5-31 Overlay settings—GPS position





Figure 5-32 Overlay settings—custom overlay




Table 5-10 Overlay setting parameter description

Parameter	Description		
	Privacy masking refers to setting a certain region in the monitoring screen		
	to protect privacy.		
	• To draw a privacy mask in the live view, click Draw .		
Privacy Masking	• To delete a privacy mask, click Delete .		
	• To clear all privacy masks, click Clear .		
	You can set the number, type and color of the privacy mask. To view a		
	privacy mask, click Go to .		
Channel Title	Set whether to display the channel title on the monitoring screen. You can		
	adjust the channel title location by dragging the box.		
	Click 🕂 to add a channel title. You can also select the Text Align of the channel title.		
Time Title	Set whether to display time on the monitoring screen, and you can select		
	whether to display the week. You can adjust the time title location by		
	dragging the box.		



Parameter	Description
OSD info	 If you want to display preset title, temperature, PTZ life warning, coordinates, zoom, north direction, RS485, and other information on the monitoring screen, you can set OSD info. Preset: Set the duration of the preset title displaying on the screen. You can select from Disable, 5s, 15s, Display Permanently, and Custom. Temperature: Select the Enable check box, select the termperature unit, and then the internal termperature of the Device is displayed. PTZ Life Warning: When the PTZ lifespan is close to the threshold, a warning will be displayed on the Live interface. This OSD info is enabled by default. Coordinates/Zoom/North/RS485/Text Overlay: Select the Enable check box to display the corresponding OSD info on the screen. You can adjust the OSD info location by dragging the box.
Font Attribute	• There are two options for alignment of text overlay: Left and Right. Set the font of the channel title, time title, and OSD info, and you can also set the color and size of the font.
Picture Overlay	Set whether to display the overlaid picture on the monitoring screen. Click Upload Picture to overlay local pictures on the monitoring screen. You can adjust the location of an overlaid picture by dragging the yellow box.
Abnormal	Set whether to display abnormality information on the monitoring screen.
Custom Overlay	Add custom OSD information on the monitoring screen. Click F to add one line of custom OSD information. You can also select the Text Align of the channel title.

5.1.2.4 ROI


ROI is available on select models.

Set a key monitoring region as a ROI (region of interest). You can set the image quality of this region.

<u>Step 1</u> Select Setting > Camera > Video > ROI.

The **ROI** interface is displayed. See Figure 5-33.





<u>Step 2</u> Select **Enable** to enable this function.

<u>Step 3</u> Press and hold the left mouse button to draw boxes on the monitoring screen. You can draw up to 4 boxes.

- Click **Delete** or right click to delete the drawn boxes.
- Click **Remove All** to clear all boxes.
- <u>Step 4</u> Set the image quality of the ROI.
- Step 5 Click Save.

5.1.2.5 Path

The storage path is associated with the snapshot and recording on the **Live** interface. You can set the path of **Live Snapshot** and **Live Record** respectively.

The storage path is associated with the snapshot, downloaded and clipped files on the **Playback** interface. You can set the path of **Playback Snapshot**, **Playback Download**, and **Video Clips** respectively.

<u>Step 1</u> Select Setting > Camera > Video > Path.

The **Path** interface is displayed. See Figure 5-34.



Figure 5-34 Path settings

Video	Snapshot	Overlay	ROI		Path
Live Snapshot	C:\Users\	Browse			
Live Record	C:\Users\	Browse			
Playback Snapshot	C:\Users\	Browse			
Playback Download	C:\Users\	Browse			
Video Clips	C:\Users\\Users\\Users\\Users\\Users\\Users\\Users\\Users\\Users\\Users\\Users\\Users\User				Browse
	Default	Save			

<u>Step 2</u> Set each storage path.

- Default storage path for snapshots:
 C:\Users\admin\WebDownload\LiveSnapshot.
- Default storage path for recording: C:\Users\admin\WebDownload\LiveRecord.
- Default storage path for playback snapshot: C:\Users\admin\WebDownload\PlaybackSnapshot.
- Default storage path for playback download: C:\Users\admin\WebDownload\PlaybackRecord.
- Default storage path for video clips: C:\Users\admin\WebDownload\VideoClips.

admin is the login account.

Step 3 Click Save.

5.1.3 Audio

This function is available on select models.

5.1.3.1 Audio

Set audio parameters of the Device.

<u>Step 1</u> Select Setting > Camera > Audio > Audio.

The **Audio** interface is displayed. See Figure 5-35.



Figure 5-35 Audio settings

Main Stream	
Enable	
Encode Mode	G.711A 🗸
Sampling Frequency	8000 🗸
Sub Stream	
Enable	Sub Stream 1
Encode Mode	G.711A 🗸
Sampling Frequency	8000 🗸
Attribute	
AudioIn Type	Lineln V
Noise Filter	Disable V
Microphone Volume	
Speaker Volume	E 50

<u>Step 2</u> Configure parameters as needed. For parameter description, see Table 5-11.

Parameter	Description	
Enable	Enable Main Stream or Sub Stream , and then the network stream contains both audio and video; otherwise, it is only video stream.	
	Audio can be enabled only when video has been enabled.	
Encode Mode	The audio encoding modes include G.711A, G.711Mu, G726, PCM, MPEG2-Layer2, G.722.1, G.729, and AAC. It is G.711A by default.	
	The audio encoding mode set here applies to both audio streams and voice talks.	
Sampling Frequency	The supported sampling frequencies include 8000, 16000, 32000, 48000, and 64000. The sampling frequency varies depending on the encoding mode. Select an encoding mode as needed.	
AudioIn Type	Set the audio input type. You can select Lineln or Mic.	
Noise Filter	Set whether to enable noise filter. The function is enabled by default.	



Parameter	Description
NR (Noise Reduction) Level	Adjust the noise reduction level from 0 to 100.
Microphone Volume	Adjust the microphone volume from 0 to 100.
Speaker Volume	Adjust the speaker volume from 0 to 100.

Step 3 Click Save.

5.2 Network Settings

5.2.1 TCP/IP

You can configure the IP address and DNS server of the Device to connect it to other devices in the network.

Before configuring network parameters, make sure that the Device is connected to the network properly.

- If there is no router in the network, assign an IP address in the same network segment.
- If there is a router in the network, set the corresponding gateway and subnet mask.

<u>Step 1</u> Select Setting > Network > TCP/IP.

The TCP/IP interface is displayed. See Figure 5-36.



Figure 5-36 TCP/IP settings

TCP/IP	
Host Name	IPDome
Ethernet Card	Wire(Default)
Mode	Static O DHCP
MAC Address	
IP Version	IPv4 V
IP Address	
Subnet Mask	
Default Gateway	
Preferred DNS	
Alternate DNS	
MTU	1500 (600~1500)
Enable ARP/Ping to see the second	et IP address service
	Default Refresh Save

 $\underline{Step \ 2} \quad Set \ TCP/IP \ parameters. \ For \ details, \ see \ Table \ 5-12.$

Parameter	Description	
Host Name	Set the name of the current device. The host name can be English or	
	Chinese within 63 bytes.	
	Select the Ethernet card to be configured. Wire is selected by default.	
Ethernet Card	If the Device is configured with multiple Ethernet cards, the default	
	Ethernet card can be changed. If you reset the default Ethernet card,	
	restart the Device.	
	Static and DHCP modes are available.	
	• If DHCP is selected, the IP address is obtained automatically. In this	
Mode	case, the IP address, subnet mask, and gateway cannot be set.	
	• If Static is selected, you need to set the IP address, subnet mask, and	
	gateway manually.	
MAC Address	Display the MAC address of the Device.	
IP Version	You can select IPv4 or IPv6 . Both versions are supported and can be	
IP version	accessed.	
IP Address	Enter correct digits to change the IP address.	
Subnet Mask	Set the subnet mask according to actual conditions. The subnet prefix is a	
	number in the range of 1 to 255. The subnet prefix identifies a specific	
	network link, and usually contains a hierarchical structure.	



Parameter	Description		
	The Device checks the validity of all IPv6 addresses. The IP address and		
	the default gateway must be in the same network segment. Make sure that		
	a certain part of the subnet prefix in the IP address and default gateway		
	are the same.		
Default	Configure as needed. The default gateway		
Gateway	must be in the same network segment as the IP	For IPv6 version, in the	
-	address.	IP Address, Default	
Preferred DNS	IP address of the DNS server. Gateway, Preferred		
		DNS, and Alternate	
Alternate DNS	Alternate IP address of the DNS server.	DNS fields, enter 128	
		bits, and these fields	
		cannot be blank.	
	You can set the MTU value to ensure good data	-	
	the network. The value is 1500 by default. Modifying MTU value causes		
	ethernet card restarting and network disconnection.		
MTU	Here are some suggested value for your reference.		
WITO	 1500: It is the maximum and default value of Ethernet packet, typical setting of the network connection without PPPOE or VPN, and is the 		
	default setting of some routers, network adapters, and switches.		
	 1492: The optimal value for PPPOE. 		
	 1468: The optimal value for DHCP. 		
	 1450: The optimal value for VPN. 		
	Select the check box, and then you can modify and set the device IP		
	address through ARP/Ping command if the MAC	address is known.	
Enable	The function is enabled by default. During reboot, you will have no more		
ARP/Ping to set	than 2 minutes to configure the Device IP address by a ping packet with		
IP address	certain length. The server will be turned off in 2 n	ninutes, or it will be turned	
service	off immediately after the IP address is successfu	lly configured. If the	
	function is not enabled, the IP address cannot be	e configured with ping	
	packet.		

Step 3 Click Save.

An Example of Configuring IP Address with ARP/Ping

- <u>Step 1</u> To obtain a usable IP address, make sure that the Device and your PC are in the same LAN.
- <u>Step 2</u> Get the MAC address from the Device label.
- <u>Step 3</u> Open command editor on the PC and enter the following command. See Table 5-13.

System	Command	
Windows syntax	arp -s <ip address=""> <mac></mac></ip>	
	ping -I 480 -t < IP Address >	
	Example:	
	arp -s 192.168.1.125 11-40-8c-18-10-11	

Table 5-13 Command lists



System	Command	
	ping -l 480 -t 192.168.0.125	
UNIX/Linux/Mac syntax	arp -s <ip address=""> <mac></mac></ip>	
	ping -s 480 < IP Address >	
	Example:	
	arp -s 192.168.1.125 11-40-8c-18-10-11	
	ping -s 480 192.168.0.125	
	netsh i i show in	
	netsh -c "i i" add neighbors ldx <ip address=""> <mac></mac></ip>	
Win7 syntax	ping -I 480 -t < IP Address >	
	Example:	
	netsh i i show in	
	netsh -c "i i" add neighbors 12 192.168.1.125	
	11-40-8c-18-10-11	
	ping -l 480 -t 192.168.1.125	

Step 4 Power off the Device and then restart it, or restart the Device over the network.

- Step 5 Check the PC command line. If there is information such as "Reply from 192.168.1.125...", it means the configuration succeeds. In this case, you can close the command editor.
- <u>Step 6</u> Enter *http://<IP address>* in the browser address bar to log in.

5.2.2 Port

Configure the maximum port numbers and values on this interface.

<u>Step 1</u> Select Setting > Network > Port.

The **Port** interface is displayed. See Figure 5-37.

Figure 5-37 Port interface

	9	
Port		
		_
Max Connection	10	(1~20)
TCP Port	37777	(1025~65534)
UDP Port	37778	(1025~65534)
HTTP Port	80	
RTSP Port	554	
HTTPS Port	443	
	Default	efresh Save
Of	turbus of the Device Ford	

Except Max Connection, modifications of other parameters will take effect after

<u>Step 2</u> Configure each port value of the Device. For details, see Table 5-14.

69

- Ш

restart.

•



- 0–1024, 1900, 3800, 5000, 5050, 9999, 37776, 37780–37880, 39999, and 42323 are occupied for specific uses.
- It is not recommended to use the default values of other ports during port configuration.

Parameter	Description	
Max	The maximum number of users that can log in to the web interface of the	
Connection	Device simultaneously. The value ranges from 1 to 10, and it is 10 by default.	
TCP Port	TCP service port. The value is 37777 by default. You can set this parameter	
TOFFOIL	as needed.	
UDP Port	User Datagram Protocol port. The value is 37778 by default. You can set this	
	parameter as needed.	
HTTP Port	HTTP communication port. The value is 80 by default. You can set this	
	parameter as needed.	
	Real Time Streaming Protocol port. Keep the default value 554 if it is	
	displayed. If you play live view through Apple's QuickTime or VLC, the	
	following format is available. This function is also supported by Blackberry	
	mobile phone.	
	When the URL format requiring RTSP, you need to specify channel number	
	and bit stream type in the URL, and also username and password if needed.	
	When playing live view with Blackberry mobile phone, you need to disable the	
	audio, and then set the stream encoding mode to H.264B and resolution to	
	CIF.	
	URL format example:	
	rtsp://username:password@ip:port/cam/realmonitor?channel=1&subtype=0	
	Username: Your username. For example, admin.	
	Password: Your password. For example, admin.	
RTSP Port	IP: Your device IP. For example, 192.168.1.122.	
	• Port: Leave it if the value is 554 by default.	
	• Channel: Channel number starting from 1. For example, if it is channel 2,	
	then enter channel=2.	
	• Subtype: stream type. The main stream is 0 (subtype=0); the sub stream	
	is 1 (subtype=1).	
	For example, if you require the sub stream of channel 2 from a certain device,	
	then the URL shall be:	
	rtsp://admin:admin@192.168.1.123:554/cam/realmonitor?channel=2&subtyp	
	e=1	
	If certification is not required, you do not need to specify the username and	
	password. Use the following format:	
	rtsp://ip:port/cam/realmonitor?channel=1&subtype=0	
	A network protocol for real-time data communication. The value is 1935 by	
	default. You can enter the value as needed.	
RTSP Port		
	Enable RTMP to push audio and video data to the third-party server. Make	
	sure that the address is trusted; otherwise it might cause data leakage.	

Table 5-14 Port parameter description



Parameter	Description
HTTPS Port	HTTPS communication port. The value is 443 by default. You can set this
	parameter as needed.

Step 3 Click Save.

5.2.3 PPPoE

You can enable PPPoE (Point-to-Point Protocol over Ethernet) to establish network connection. In this case, the Device obtains a dynamic IP address. To use this function, you need to obtain the PPPoE username and password from the Internet Service Provider (ISP).

<u>Step 1</u> Select Setting > Network > PPPoE.

The **PPPoE** interface is displayed. See Figure 5-38.

Figure 5-38 PPPoE interface (1)

PPPoE	
Enable	
Username	none
Password	
	Default Refresh Save

<u>Step 2</u> Select **Enable**, and then enter PPPoE username and password.

Step 3 Click Save.

Save Succeeded! is displayed, and the obtained IP address of public network is displayed in real time. See Figure 5-39. You can access the Device through the IP address.

Figure	5-39	PPPoE	interface	(2)
--------	------	-------	-----------	-----

PPPoE		
Enable		
Username	public	
Password	•••••	
	Default Refresh Save	

5.2.4 DDNS

Properly configure DDNS, and then the domain name on the DNS server matches your IP address and refresh the matching relation in real time. You can always access your device with



the same domain name no matter how much your device IP address changes. Before making any changes, check whether your device supports the DNS server.

 \square

- The third party servers might collect your device information if DDNS is enabled.
- Register and log in to the DDNS website, and then you can view the information of all the connected cameras in your account.

```
<u>Step 1</u> Select Setting > Network > DDNS.
```

The **DDNS** interface is displayed. See Figure 5-40.

Figure 5-40 DDNS

DDNS	
🗹 Туре	NO-IP DDNS After enabling DDNS function, third-party server may collect your device info.
Address	dynupdate.no-ip.com
Domain Name	none test
Username	none
Password	••••
Interval	1440 Min.(1440~2880)
	Default Refresh Save

<u>Step 2</u> Select **Type**, and then configure the parameters as needed. For details, see Table 5-15.

Parameter	Description		
Туре	The name and website of the DDNS service provider. Here is the matching		
	relationship: ● CN99 DDNS		
	Server address: www.3322.org		
Server address	NO-IP DDNS		
	Server address: dynupdate.no-ip.com		
	Dyndns DDNS		
	Server address: members.dyndns.org		
Domain Name	The domain name you registered on the DDNS website.		
Username	Enter the username and password obtained from DDNS service provider.		
Password	You need to register an account (including username and password) on		
Password	the website of DDNS service provider.		
Interval	The update cycle of the connection between your device and the server,		
	and the time is 10 minutes by default.		

Step 3 Click Save.

Open the browser, enter the domain name in the address bar, and then press the Enter key. The login interface is displayed.

a hua

5.2.5 SMTP (Email)

After this function is enabled, the device data will be sent to the given server. There is data leakage risk. Think twice before enabling the function.

Configure **SMTP (Email)**. When alarms, video detection and abnormal events are triggered, an email will be sent to the recipient server through SMTP server. The recipient can log in to the incoming mail server to receive emails.

<u>Step 1</u> Select Setting > Network > SMTP (Email).

The SMTP (Email) interface is displayed. See Figure 5-41.

Figure 5-41 SMTP (Email)

SMTP(Email)	
SMTP Server	none
Port	25
Anonymity	
Username	anonymity
Password	••••
Sender	none
Authentication	TLS V
Title	Message Attachment
Mail Receiver	+
Health Mail	Update Period 60 s(1~3600)
	Test
	Default Refresh Save

Step 2 C	Configure parameters	as needed. For	parameter of	description, see	Table 5-16.
----------	----------------------	----------------	--------------	------------------	-------------

Table 0-10 Civiti (Email) parameter description					
Parameter	Description				
SMTP Server	IP address of the outgoing mail server				
Sivi i P Server	complying with SMTP protocol.	_	11		
	Port number of the outgoing mail server	For	the	a	etailed
Port	complying with SMTP protocol. It is 25 by	configu	ration,	see	Table
		5-17.			
	default.	• 17.			

Table 5-16 SMTP (Email) parameter description



Parameter	Description		
Username	Username of sender mailbox.		
Password	Password of sender mailbox.		
Anonymity	For servers supporting anonymous email, you can log in anonymously without entering username, password, and sender information.		
Sender	Email address of the sender.		
Authentication	 Select authentication type from None, SSL and TLS. TLS is selected by default. For the detailed configuration, see Table 5-17. There might be risks if you select the authentication type other than TLS. TLS is recommended. 		
Title	You can enter no more than 63 characters in Chinese, English, and Arabic numerals.		
Mail Receiver	Email address of the receiver. Support 3 addresses at most.		
Attachment	Select the check box to support attachment in the email.		
Health Mail	The system sends test mail to check if the connection is successfully configured. Select the Health Mail check box and configure the Update Period , and then the system sends test mails according to the defined period.		
Test	Test whether the email function is normal. If the configuration is correct, the email address of the receiver will receive the test email. Save the email configuration before running rest.		

For common email configurations, see Table 5-17.

Туре	SMTP Server	Authentication	Port	Description		
QQ	smtp.qq.com	SSL	465 587	 The authentication type cannot be None. You need to enable SMTP service in your mailbox. The authentication code is required; either the QQ password or email password is not applicable. Authentication code is the code you receive when enabling SMTP service. 		
163	smtp.163.com	SSL	465/ 994	You need to enable SMTP service in your mailbox.		
		TLS	25	• The authentication code is		

Table 5-17 Common email configuration description

Туре	SMTP Server	Authentication	Port	Description	
				required; the email password	
			25	is not applicable.	
			20	Authentication code is the code	
				you receive when enabling SMTP	
				service.	
Sina	smtp.sina.com	SSL	465	You need to enable SMTP service	
Sina		—	25	in your mailbox.	
126	amta 126 aam		05	You need to enable SMTP service	
120	smtp.126.com		25	in your mailbox.	

Step 3 Click Save.

5.2.6 UPnP

After UPnP is enabled, Intranet service and port of the Device will be mapped to Extranet. Think twice before enabling it.

UPnP (Universal Plug and Play) allows you to establish the mapping relationship between Intranet and Extranet. Extranet users can access Intranet device by visiting Extranet IP address. Intranet port is device port and Extranet port is router port. Users can access the Device by accessing Extranet port. When you are not using routers for UPnP, disable UPnP to avoid affecting other functions.

Once UPnP is enabled, the Device supports UPnP protocol. In Windows XP or Windows Vista, after UPnP is enabled, the Device can be automatically searched by Windows network.

Perform the following steps to add UPnP network service in the Windows system.

- Step 1 Open Control Panel, and select Add or Remove Programs.
- Step 2 Click Add/Remove Windows Components.
- <u>Step 3</u> Select **Network Service** from the **Windows Components Wizard** and click **Details** button.
- <u>Step 4</u> Select Internet Gateway Device Discovery and Control Client, and UPnP User Interface, and then click OK to start installation.

Perform the following steps to configure UPnP:

<u>Step 1</u> Select Setting > Network > UPnP.

The **UPnP** interface is displayed. See Figure 5-42.

Figure 5-42 UPnP

rt Mapping List						
	Service Name	Protocol	Internal Port	External Port	Status	Modify
×	HTTP	WebService TCP	80	8080	Mapping Failed	1
¥	TCP	PrivService:TCP	37777	37777	Mapping Failed	1
	UDP	PrrvService.UDP	37778	37776	Mapping Failed	1
X	RTSP	RTSPService.TCP	554	554	Mapping Failed	*



Step 2 Select Enable.

<u>Step 3</u> Select a mode from the drop-down list.

There are 2 mapping modes: Custom and Default. In Custom mode, users can modify the external port. Select Default, and then the system finishes mapping with unoccupied port automatically. In this case, you do not need to modify mapping relation.

Step 4 Select Start Device Discover as needed.

Step 5 Click Save.

5.2.7 SNMP

SNMP (Simple Network Management Protocol) is a basic network management framework. You need to install certain software to the Device to obtain the configuration information of the Device.

The following requirements must be satisfied if you want to use SNMP function:

- Install SNMP monitoring and managing tools, such as MIB Builder and MG-SOFT MIB Browser.
- Obtain two MIB files corresponding to the current version from the technical personnel.

Step 1 Select Setting > Network > SNMP.

The **SNMP** interface is displayed. See Figure 5-43 and Figure 5-44.

Figure 5-43 SNMP (1) SNMP Version v1 v2 v3 (Recommen... SNMP Port 161 $(1 \sim 65535)$ Read Community Write Community Trap Address Trap Port 162 Keep Alive Default Refresh Save



Figure 5-44 SNMP (2)

SNMP			
Version	□ v1	□ v2	2 v2 (Pasamman
Version	v1	v2	V3 (Recommen
SNMP Port	161	(1~6	5535)
Read Community			
Write Community			
Trap Address			
Trap Port	162		
Keep Alive			
Read-only Username	public		
Authentication Type	MD5	⊖ SHA	
Authentication Pass			ninimum pass phrase length is 8 characters
Encryption Type	CBC-DES		minimum pass prirase lengur is o characters
	CBC-DE3	The	ninimum pass phrase length is 8 characters
Encryption Password			minimum pass prirase lengtr is o characters
Read&write Userna	private		
Authentication Type	MD5	⊖ SHA	
Authentication Pass		The	ninimum pass phrase length is 8 characters
Encryption Type	• CBC-DES		
Encryption Password		The	minimum pass phrase length is 8 characters
	Default	Refresh	Save

Step 2 Select a version to enable SNMP.

In the **Trap Address** field, enter the IP address of the PC that has MG-SOFT MIB Browser installed, leaving other parameters to the default values.

	Table 5-10 Stilling parameter description
Parameter	Description
Version	 Select the check box of the version you need, and the system can process information of the corresponding version. Select V1, and the system can only process information of V1 version. Select V2, and the system can only process information of V2 version. Select V3, and then V1 and V2 become unavailable. You need to set the username, password, and authentication type to visit your device from the server. V1 and V2 might cause data leakage, and V3 is recommended.
SNMP Port	The listening port of the software agent in the Device.



Parameter	Description
Read Community/Write	The read and write community strings that the software agent supports.
Community	The name can only consist of number, letter, underline (_), and strikethrough (-).
Trap Address	The target address of the trap information sent by the software agent in the Device.
Trap Port	The target port of the trap information sent by the software agent in the Device.
Keep Alive	Select the Keep Alive check box, and the system can send data package to ensure network connection without interruption.
Read-only Username	The name is public by default.
	The username can only consist of number, letter, and underline.
Read&write Username	The name is private by default.
	The username can only consist of number, letter, and underline.
Authentication Type	You can select from MD5 and SHA , and it is MD5 by default.
Authentication	It shall be no loss than 8 digits
Password	It shall be no less than 8 digits.
Encryption Type	It is CBC-DES by default.
Encryption Password	It shall be no less than 8 digits.

Step 3 Click Save.

Step 4 View device information.

- 1) Run MIB Builder and MG-SOFT MIB Browser.
- 2) Compile the two MIB files with MIB Builder.
- 3) Load the generated modules with MG-SOFT MIB Browser.
- 4) Enter the IP address of the Device you need to manage in the MG-SOFT MIB Browser, and then select version to search.
- 5) Expand all the tree lists displayed in the MG-SOFT MIB Browser, and then you can view the configuration information, video channel amount, audio channel amount, and software version.

Use PC with Windows operating system (OS) and disable SNMP Trap service. The MG-SOFT MIB Browser will display prompt when an alarm is triggered.

5.2.8 Bonjour

Bonjour is also called zero-configuration networking, which can automatically discover computers, devices and services on IP networks. Bonjour is a protocol of industry standard which allows devices to search and find each other. IP address or DNS server is not required during the process.



Enable this function, and the network camera will be automatically detected by the OS and client with Bonjour function. When the network camera is automatically detected by Bonjour, server name you have set will be displayed.

<u>Step 1</u> Select Setting > Network > Bonjour.

The **Bonjour** interface is displayed. See Figure 5-45.

Figure 5-45 Bonjour interface

Bonjour			
Z Enable			
Server Name	1000100100000	Fill	
	Default	Refresh	Save

<u>Step 2</u> Select **Enable**, and then set **Server Name**.

Step 3 Click Save.

In the OS and clients that support Bonjour, perform the following steps to visit the web interface of the Device with Safari browser.

- Step 1 Click Show all bookmarks in Safari.
- <u>Step 2</u> The OS or client automatically detects the network cameras with Bonjour enabled in the LAN.
- <u>Step 3</u> Click to visit the corresponding web interface.

5.2.9 Multicast

Access the Device by network to see live view. If the access times exceed its upper limit, preview might fail. You can set multicast IP to access by multicast protocol to solve the problem. The Device supports two multicast protocols: **RTP** and **TS**. RTP is enabled by default when main stream and sub stream are used. TS is disabled by default.

5.2.9.1 RTP

<u>Step 1</u> Select Setting > Network > Multicast > RTP.

The **RTP** interface is displayed. See Figure 5-46.

Figure 5-46 RTP interface

Main Stream			Sub Stream		
Enable			Enable	Sub Stream 1]
Multicast Address	51.1.2.1		Multicast Address	St. 1 . 2 . 1	
	(224.0.0.0~239.255.255.255)			(224.0.0.0~239.255.255.255)	
Port	40000	(1025~65500)	Port	40016	(1025~65500)

<u>Step 2</u> Enable main stream or sub stream as needed. Step 3 Enter multicast address and port number.



Step 4 Click Save.

5.2.9.2 TS

<u>Step 1</u> Select Setting > Network > Multicast > TS. The TS interface is displayed. See Figure 5-47.

Figure 5-47 TS interface

Main Stream		Sub Stream	
Enable		Enable	Sub Stream 1
Multicast Address	10. 1. F. I.	Multicast Address	E9. 1. E. B
	(224.0.0.0~239.255.255.255)		(224.0.0.0~239.255.255.255)
Port	20000 (1025~65500)	Port	20016 (1025~65500)
	Default Refresh	Save	

<u>Step 3</u> Enter multicast address and port number.

Step 4 Click Save.

5.2.10 Auto Register

After you enable this function, when the Device is connected to Internet, it will report the current location to the specified server which acts as the transit to make it easier for the client software to access the Device.

<u>Step 1</u> Select Setting > Network > Auto Register.

The Auto Register interface is displayed. See Figure 5-48.

Figure 5-48 Auto register

Auto Register	
Enable	
IP Address	0.0.0.0
Port	7000
Sub-Device ID	none
	Default Refresh Save

<u>Step 2</u> Select the **Enable** check box to enable **Auto Register**.

Step 3 Enter IP Address, Port and Sub-Device ID. For details, see Table 5-19.



Table 5-19 Auto register parameter description			
Parameter	Description		
IP Address	The IP address of server that needs to be registered to.		
Port	The port for auto-registration.		
Sub-Device ID	Sub device ID assigned by server.		
Stop 4 Click Save			

Step 4 Click Save.

5.2.11 Wi-Fi

Devices with Wi-Fi function can access network through Wi-Fi.

- Wi-Fi and WPS are available on select models.
- All devices with WPS button support WPS function.

5.2.11.1.1 Wi-Fi

The name, status and IP information of current hotspot are displayed in the Wi-Fi information bar. Click **Refresh** after reconnection to make sure that the operating status is displayed in real time. Connecting Wi-Fi hotspot takes some time depending on network signal strength. For Wi-Fi configuration interface, see Figure 5-49.

] Enable				Add SSID Search SSI
ID List			0.000	
	SSID	Connect mode	Authanize Mode	Signal Quality
Witi Info				
SSIO				
SSID IP Address				
Wifi Info SSID IP Address Subnet Mask Gateway				

Perform the following steps to configure Wi-Fi.

Step 1 Select the Enable check box.

<u>Step 2</u> Click **Search SSID**, and Wi-Fi hotspots in the environment of current network camera are displayed. See Figure 5-50.

	SSID	Connect mode	Authorize Made	Signal Quality
	manufacture de la constante	Auto	WPAMPA2-PSK-AES	
	Instantia (Province)	Auto	WPA/WPA2-P5K-AE5	
	ALCONT. N. CONT.	Auto	WPA2-PSK-AES	
	10.00	Auto	WPA/WPA2-PSK-AES	
	Series and	Auto	WPA2-PSK-AES	-
10	41.818-	Auto	WPA/WPA2-PSK-AES	-
fi Info ID Address bret Mask dewky	Connected			

<u>Step 3</u> To manually add Wi-Fi, click **Add SSID**, and the **Add WiFi** interface is displayed. See Figure 5-51.

<u>Step 4</u> Enter a network name in the dialog box.



It is recommended to set a secure encryption method for the Device to connect routers. Figure 5-51 Adding Wi-Fi

Add WIFI		×
SSID		
	ОК Са	ncel

- <u>Step 5</u> Double-click one hotspot to display the **Signal Quality** and the **Authentication Manner**.
 - If the password is required, enter it. When entering the password, its index number shall be consistent with that on the router.
 - Click **Connection** if password is not required.

5.2.11.1.2 WPS

For WPS configuration interface, see Figure 5-52.

Figure 5-52 WPS setting

WIFI	WPS
Enter PIN	
PIN	
SSID	
O Button	
Status	Connected
	Connection Refresh

PIN and SSID can be obtained from the router. Enter PIN and SSID, and then click **Refresh** to display operating status in real time.

5.2.12 802.1x

802.1x is a port-based network access control protocol. It allows users to manually select authentication mode to control device access to LAN, and meet authentication, billing, safety and management requirements of the network.

<u>Step 1</u> Select Setting > Network > 802.1x.

The **802.1x** interface is displayed, see Figure 5-53.



Figure 5-53 802.1x interface

802.1x			
Enable			
Authentication	PEAP	~	
Username	none		
Password	••••		
	Default	Refresh	Save

Step 2 Select the Enable check box to enable 802.1x.

<u>Step 3</u> Select an authentication mode, and enter username and password. For parameter description, see Table 5-20.

Table 5-20 802.1X setting parameter description

Description
PEAP (protected EAP protocol).
The username that was authenticated on the server.
Corresponding password.

Step 4 Click Save.

5.2.13 QoS

QoS (Quality of Service) is a network security mechanism, and is also a technology to solve network delay, congestion, and other problems. For network business, QoS includes transmission bandwidth, time delay in transmission, and packet loss of data. In network, QoS can be improved by ensuring transmission bandwidth, and reducing time delay in transmission, packet loss rate, and delay jitter.

For DSCP (Differentiated Services Code Point), there are 64 priority degrees (0–63) of data packets. 0 represents the lowest priority, and 63 the highest priority. Based on the priority, the packets are classified into different groups. Each group occupies different bandwidth and has different discard percentage when there is congestion so as to improve service quality.

<u>Step 1</u> Select Setting > Network > QoS.

The **QoS** interface is displayed. See Figure 5-54.

Figure 5-54 QoS interface

QoS			
Realtime Monitor	0	(0~63)	
Command	0	(0~63)	
	Default	Refresh	Save



<u>Step 2</u> Configure **Realtime Monitor** and **Command**. For parameter description, see Table 5-21.

Table 5-21 QoS setting parar	meter description
------------------------------	-------------------

Parameter	Description
Realtime Monitor	Data packet of network video monitoring. The value ranges from 0 to 63.
Command	Data packet of device configuration and query. The value ranges from 0 to 63.

Step 3 Click Save.

5.2.14 4G

5.2.14.1 Dialing Setting

Log in to web interface, select **Setting > Network > 4G > Dialing Setting** and the **Dialing Setting** interface is displayed. See Figure 5-55.

Camera	Dialing Setting Mol	bile Settings		
Network				
> TCP/IP	Wireless Net Type	Auto	 Enable 	
> Port	APN			
> PPPoE	Authorize Mode		*	
> DDNS	Dial-up Number			
> SMTP(Email)	Username	1.000		
> UPnP	Password	1		
> SNMP	Interval	30	£	
> Bonjour	Time Range	Setup		
> Multicast				
> 802.1x	SIM State			
> QoS	Network Support			
> 4G	Wireless Network S	itate		
> Access Platform	IP Address	hate		
PTZ				
Event	Wireless Signal			
Storage		Default	Refresh	Save
System				
Information				

Figure 5-55 Dialing setting interface

Some devices only support certain mobile carriers, and only the supported carriers are

displayed in **Network Support**.

<u>Step 1</u> Select the **Enable** check box.


<u>Step 2</u> Enter **APN**, **Authorize Mode**, **Dial-up Number**, **Username**, and **Password** according to the SIM card inserted.



These parameters might vary by countries. Contact local carrier or customer service for details.

- <u>Step 3</u> Set the period to use 4G. See Figure 5-56.
 - - If the current time is in the period you set, 4G network connection will be enabled. The IP address of the SIM card will be displayed in IP Address. And you can access the device through 4G after finishing the rest steps.
 - If the current time is not in the period you set, 4G network connection will not be enabled. Only the corresponding Wireless Signal is displayed on the interface. And you cannot access the device through 4G.

Figure 5-56 Period setting



<u>Step 4</u> Set the interval to enable 4G through message or phone call if you want to use 4G outside the period set in Step 3.

Ш

The value range is 0–7200 s and it is 30 s by default. If the interval is 30 s, after activating 4G, you can use it for 30 s. After 30 s, you need to activate 4G again. If you set the interval to 0 s, you can use 4G without disconnection and you do not need to activate it again. For the method to activate 4G through message or phone call, see "4.2.12.2 Mobile Setting."

Step 5 Click Save.

5.2.14.2 Mobile Setting

Log in to web interface, select **Setting > Network > 4G > Mobile Settings**, and the **Mobile Setting** interface is displayed. See Figure 5-55.



You can add the phone number to receive alarms. You also can add phone number used to activate 4G through message or phone call if you want to use 4G outside the period set in Step 3 of "5.2.14.1 Dialing Setting."

 \wedge

Make sure that you add international calling codes before the phone number to avoid unnecessary charges caused by phone calls or messages to other countries or regions. Figure 5-57 Mobile setting interface

Camera	Dialing Setting	Mobile Settings							
Network		-							
> TCP/IP	Message \$	Send		Message /	Activation		Phone Act	ivation	
> Port	Receiver		+	Sender		+	Caller		+
> PPPoE		Concensus of	-		Contractory (-		1.00000000000	-
> DDNS									
> SMTP(Email)		The phone number used to			The phone number used to			The phone number used to	
> UPnP		receive alarm			send activation message			make activation	
> SNMP		message			message			call	
> Bonjour									
> Multicast	Title	Event Message							
> 802.1x									
> QoS									
> 4G									
> Access Platform			efault	Refresh	Save	_			
▶ PTZ			elault	Refresh	Save				
▶ Event									
Storage									
▶ System									
▶ Information									

- **Message Send**: When alarms are triggered, the phone number added will receive message.
- Message Activation: You can enable 4G through message outside the period you set to use 4G. You need to send "ON" or "OFF" to phone number of the SIM card in the Device. "ON" indicates enabling, and "OFF" indicates disabling.
- **Phone Activation**: You can enable 4G through phone calls outside the period you set to use 4G. You need to call the phone number of the SIM card in the Device. If the call gets through, it means 4G has been enabled.

Ш

- Make sure that your SIM card supports making phone calls and sending messages, and it can be used normally.
- Make sure that you use activation function outside the time range you set; otherwise it does not work.
- <u>Step 1</u> Select the check box of the service you need to enable. You can select one or more services.


Step 2 Enter the phone number and click 🔛 to add it.

- Step 3 Click Save.
- <u>Step 4</u> Select the **Message Link** check box on the interface of the event for which you want to receive message.

Take Face Detection for example. Click **Setting > Event > Face Detection** and select the **Message Link** check box.



Figure 5-58 Message link



<u>Step 5</u> Click **Save** on the interface of the corresponding event. And you will receive message if the alarm is triggered.

5.2.15 Access Platform

5.2.15.1 P2P

P2P is a private network traversal technology which enables users to manage devices easily without requiring DDNS, port mapping or transit server. Scan the QR code with your smart phone, and then you can add and manage more devices on your mobile client.

<u>Step 1</u> Select Setting > Network > Access Platform > P2P.

The **P2P** interface is displayed.



	Figure 5-59 P2P interface	
P2P	ONVIF	
Enable		
After enabling t	the function and connecting Internet, we will collect d	evice information
such as IP add	ress, MAC address, name and serial number. The co	ollected
information is o	only used for remote access of the device. If you do n	ot agree to
enable the fund	ction, please cancel the selection of check box.	
Status	Offline	
Status S/N	Offline	
S/N		Save

- P2P is enabled by default. You can manage the devices remotely.
- When P2P is enabled and the device is connected to network, the status is displayed as **Online**. We might collect the information including IP address, MAC address, device name, and serial number. The information collected is for remote access only. If you do not agree with this, you can clear the **Enable** check box.
- Step 2 Log in to mobile phone client and tap Device Management.
- Step 3 Tap Add + at the upper-right corner.
- <u>Step 4</u> Scan the QR code on the P2P interface.
- <u>Step 5</u> Follow the instructions to finish settings.

5.2.15.2 ONVIF

The ONVIF authentication is **On** by default, which allows the network video products (including video recording device and other recording devices) from other manufacturers to connect to the Service.

ONVIF is enabled by default.

<u>Step 1</u> Select Setting > Network > Access Platform > ONVIF.

The ONVIF interface is displayed. See Figure 5-60.

Figure 5-60 ONVIF interface

P2P	ONVIF		
Authentication	🖭 On 🔄 Off		
	Default	Refresh	Save



<u>Step 2</u> Select On for Authentication. <u>Step 3</u> Click **Save**.

5.2.15.3 RTMP

You can connect the third party platforms (such as YouTube) to play live video through RTMP protocol.

- Only admin user can configure RTMP.
- RTMP only supports H.264, H.264B and H.264H video formats, and Advanced Audio Coding (AAC) audio format.

<u>Step 1</u> Select Setting > Network > Access Platform > RTMP.

The **RTMP** interface is displayed. See Figure 5-61.

Figure 5-61 RTMP interface

P2P	ONVIF	RTMP	
Enable Etream Type	Main Stream	○ Sub Stream 1 ○ Sub Stream 2	
Address Type	Non-custom	⊖ Custom	
IP Address			
Port	100	(0~65535)	
Custom Address			
	Default	Refresh Save	

<u>Step 2</u> Select the **Enable** check box, and RTMP will be enabled.

When enabling RTMP, make sure that the address can be trusted.

<u>Step 3</u> Set parameters. For details, see Table 4-20.

Table 5-22 RTMP parameter setting description

Parameter	Description				
Stroom Tupo	Select live video stream type. Make sure that the video format of the				
Stream Type	stream is H.264, H.264B or H.264H, and the audio format is AAC.				
	There are two options: Non-custom and Custom .				
Address Type	Non-custom: You need to fill in the IP address or domain name.				
	Custom: You need to fill in the address allocated by the server.				
IP Address	If you have selected Non-custom , IP address and port need to be filled in.				
Dert	IP Address: IPv4 or domain name is supported.				
Port	Port: It is recommended to use the default value.				



Parameter	Description
Custom	If you have selected Custom , the address allocated by the server needs
Address	to be filled in.

Step 4 Click Save.

5.3 PTZ Settings

5.3.1 Protocol

Network PTZ setting and analog PTZ setting are available on select models.

5.3.1.1 Network PTZ Settings

<u>Step 1</u> Select Setting > PTZ > Protocol > Network PTZ.

The Network PTZ interface is displayed. See Figure 5-62.

Figure 5-62 Network PTZ setting

		-	•		
N	etwork PTZ	Analog PTZ			
	Protocol	PELCOD	~		
		Default	Refresh	Save	
<u>Step 2</u>	Select a protocol	as needed. You can s	elect DH-SD1, DI	H-SD3, PELCOD	, or PELCOP .
	DH-SD1 is selected	ed by default.			
	DH-SD1 protocol	supports up to 80 pre	esets, and DH-SI	D3 protocol supp	orts up to 300
	presets.				

Step 3 Click Save.

5.3.1.2 Analog PTZ Settings

<u>Step 1</u> Select Setting > PTZ > Protocol > Analog PTZ. The Analog PTZ interface is displayed. See Figure 5-63.



Figure 5-63 Analog PTZ setting

Network PTZ	Analog PTZ		
Address	1		
Baud Rate	9600	~	
Data Bit	8	\checkmark	
Stop Bit	1	\checkmark	
Parity	NONE	\checkmark	
	Default	Refresh	Save

<u>Step 2</u> Configure parameters as needed. See Table 5-23.

Table 5-23 Analog PTZ parameter description

Parameter	Description	
Address	Enter the address of the Device.	
	Make sure that the address is the same as the device address; othe	
	you cannot control the device.	
Baud Rate	Select the baud rate of the Device.	
Data Bit	It is 8 by default.	
Stop Bit	It is 1 by default.	
Parity	It is NONE by default.	

Step 3 Click Save.

5.3.2 Function

5.3.2.1 Preset

Select **Setting > PTZ > Function > Preset**. The **Preset** interface is displayed. See Figure 5-64.

If you click Remove All, all presets and special presets will be cleared.



Figure 5-64 Preset settings

		 Preset 	Number	Preset Title	Save	÷
	2019-11-07 15 11 26	▶ Tour	11	Preset1		•
	2019-11-07-1911120	PTZ Speed	2	Preset2		•
		Idle Motion				
Preset1 1 43 C P 0.0 T 45.0 Z 1.0		PowerUp				
		 PTZ Limit 				
		Time Task				
Section annumentation.	1 A	 PTZ Restart 				
PTZ Camera		 Default 	Number S	pecial Preset Functio	n Save Ca	all
0 0 70	om (+)					
A ↓ → For	cus 🕂					
Viv	-					

Preset

Preset means a certain position of the Device. Users can adjust the PTZ and camera to the location quickly through calling presets.

Step 1 At the lower left corner of the Preset interface, click the direction buttons,

speed 5, , , , and + to adjust the PTZ direction, speed, zoom, and focus of

the Device.

Step 2 Click 🔂 to add a preset.

The current position is set to a preset and is displayed in the list. See Figure 5-65 Figure 5-65 Adding presets

Number	Preset Title	Save	÷
1	Preset1		•
2	Preset2		•

Step 3 Click i to save the preset.

<u>Step 4</u> Perform operations on presets.

- Double-click the preset title to edit the title displayed on the monitoring screen.
- Click
 to delete the preset.




Special Preset

Special presets serve as the shortcut for some special functions switch or calling, and they no longer represent the location of the PTZ camera.

Step 1 Click 🗗 to add a special preset. The added special preset will be displayed in the list.

The number of special presets starts from 51 by default, and 100 is the largest number. Figure 5-66 Special presets



<u>Step 2</u> Click local to save the added special preset. <u>Step 3</u> Perform operations on special presets.

- Click Day/Night B&V
 to modify the special preset function.
 - Click 🤜 to delete the special preset.

Click local the function configured for the special preset.

If the PTZ is restored to default settings, all preset configurations will be cleared, but the called function will remain.

5.3.2.2 Tour

Tour means a series of movements that the Device makes along several presets.

You need to set several presets in advance.

<u>Step 1</u> Select **Setting > PTZ > Function > Tour**.

The Tour interface is displayed. See Figure 5-67.

See Figure 4-60.

Figure 5-67 Tour settings

2017-09-13 10:18:04 1	ue Four	Tour Mode Se Or		•
	 Scan Pattern Pan PTZ Speed Idle Motion 	Tour No.	Tour Name	Delete
PTZ Done	PowerUp PTZ Limit Time Task PTZ Restart		+ Add	
C→ Zoom (+) → Focus (+) → Focus (+) → Iris (+)	▶ Default	Number Pro	set Duration	i Speed Del

<u>Step 2</u> Select the **Tour Mode** from **Original Path** and **Shortest Path**. **Original Path** is selected by default.

- Original Path: Tour in the order of adding presets.
- Shortest Path: Starting from the preset with largest horizontal zoom value and vertical zoom value, pass all presets in the tour to ensure the shortest path. The Device reaches the corresponding preset and ensure the minimum number of rotation.
- <u>Step 3</u> Click **Add** at the bottom of the list at the upper right corner of the interface to add a tour path.
- <u>Step 4</u> Click **Add** at the bottom of the list at the lower right corner of the interface to add several presets.
- <u>Step 5</u> Perform tour operations.
 - Double-click tour name to edit the name of the corresponding tour.
 - Double-click duration to set the time that the Device stays at the corresponding preset.
 - Double-click speed to modify the tour speed. The default value is 7, and the value range is 1–10. The larger the value, the faster the speed.
- <u>Step 6</u> Click **Start** to start the tour.

The ongoing tour stops if any operation is made to the PTZ.


5.3.2.3 Scan

Scan means the Device moves horizontally at a certain speed between the defined left and right limits.

<u>Step 1</u> Select **Setting > PTZ > Function > Scan**.



The **Scan** interface is displayed. See Figure 5-68. Figure 5-68 Scan settings



- Step 2 Select the Scan No.
- <u>Step 3</u> Drag the slider to adjust the scan speed.
- <u>Step 4</u> Click **Setup** to adjust the Device to an ideal position.
- <u>Step 5</u> Click **Set Left Limit** and **Set Right Limit** to set the left and right boundaries of the Device.
- <u>Step 6</u> Click **Start**, and the Device starts scanning.
- <u>Step 7</u> Click **Stop**, and the scanning stops.

5.3.2.4 Pattern

Pattern means a record of a series of operations that users make to the Device. The operations include horizontal and vertical movements, zoom and preset calling. Record and save the operations, and then you can call the pattern path directly.

<u>Step 1</u> Select Setting > PTZ > Function > Pattern.

The **Pattern** interface is displayed. See Figure 5-69.



Figure 5-69 Pattern settings



- Step 2 Select the Pattern No.
- <u>Step 3</u> Click **Setup** and **Start Rec**, and then operate the PTZ as needed.
- Step 4 Click Stop Rec to stop recording.
- <u>Step 5</u> Click **Start**, and the Device starts patterning.
- <u>Step 6</u> Click **Stop**, and the patterning stops.

5.3.2.5 Pan

Pan refers to the continuous 360° rotation of the Device at a certain speed.

<u>Step 1</u> Select **Setting > PTZ > Function > Pan**.

The **Pan** interface is displayed. See Figure 5-70.

Figure 5-70 Pan settings



<u>Step 2</u> Drag the slider to set the **Pan Speed**. <u>Step 3</u> Click **Start**, and the Device starts to rotate horizontally at this speed.

5.3.2.6 PTZ Speed

You can adjust the manual control speed of the PTZ by setting PTZ speed. This speed does not apply to tour, pattern, or auto tracking.

<u>Step 1</u> Select Setting > PTZ > Function > PTZ Speed.

The **PTZ Speed** interface is displayed. See Figure 5-71.

Figure 5-71 PTZ speed settings



Step 2 Select Low, Middle or High.



5.3.2.7 Idle Motion

Idle motion refers to a set motion when the Device does not receive any valid command within a certain period.

Set Preset, Tour, Scan or Pattern in advance.

<u>Step 1</u> Select Setting > PTZ > Function > Idle Motion.

The Idle Motion interface is displayed. See Figure 5-72.

Figure 5-72 Idle motion settings



- <u>Step 2</u> Select the **Enable** check box to enable the idle motion.
- <u>Step 3</u> Select idle motion from **Preset**, **Tour**, **Scan** and **Pattern**.
- <u>Step 4</u> Select the action number of the selected motion.
- <u>Step 5</u> Set **Idle Time** for the selected motion.
- Step 6 Click Save.

5.3.2.8 PowerUp

PowerUp means the automatic operation of the Device after it is powered on.

Set Preset, Tour, Scan or Pattern in advance.

<u>Step 1</u> Select **Setting > PTZ > Function > PowerUp**.

The **PowerUp** interface is displayed. See Figure 5-73.



Figure 5-73 PowerUp settings



<u>Step 2</u> Select the **Enable** check box to enable power up motion.

Step 3 Select power up motion from **Preset**, **Tour**, **Scan**, **Pattern** or **Auto**.

Select **Auto** and the last motion before you shut down the Device last time will be performed.

- <u>Step 4</u> Select the action number of the selected motion.
- Step 5 Click Save.

5.3.2.9 PTZ Limit

E

After setting the PTZ limit, the Device can only move in the set area.

<u>Step 1</u> Select Setting > PTZ > Function > PTZ Limit.

The PTZ Limit interface is displayed. See Figure 5-74.

Figure 5-74 PTZ limit settings

2017/tl, 90-10217/82 Tue	 Preset Tour Scan Pattern Pan PTZ Speed Idle Motion PowerUp PTZ Limit 	Enable Up Line Setting Live Down Line Setting Live Please enable Coordinates at Overlay function to see PTZ Coordinates on video.
Speed 5	 Time Task PTZ Restart Default 	



<u>Step 2</u> Adjust the PTZ direction and click **Setting** to set the **Up Line**.

<u>Step 3</u> Adjust the PTZ direction and click **Setting** to set the **Down Line**.

Step 4 Click Live to preview the already-set up line and down line.

<u>Step 5</u> Select the **Enable** check box to enable the PTZ limit function.

5.3.2.10 Time Task

After setting time task, the Device performs the selected motions during the set period.

Set Preset, Tour, Scan or Pattern in advance.

<u>Step 1</u> Select Setting > PTZ > Function > Time Task.

The **Time Task** interface is displayed. See Figure 5-75.

Figure 5-75 Time task settings

	Preset Enable Faur	
A Derive (2004) A Deri	Fattern Fattern Time Task num 1 Task Set	Clear All Tour Pattern et1 • Sec. (5-3600) Copy

- Step 2 Select the Enable check box to enable time task function.
- <u>Step 3</u> Set the time task number.

Click Clear All to delete all set time tasks.

- Step 4 Select Time Task action such as Preset, Tour, Scan or Pattern.
- <u>Step 5</u> Select the action number of the selected motion.
- <u>Step 6</u> Set the time for **AutoHome**.

AutoHome refers to the time needed to automatically recover the time task in case of manually calling the PTZ to stop the time task.

- <u>Step 7</u> Click **Period setting** to set the period to perform time tasks.
- <u>Step 8</u> Select the task number to copy settings to the selected task, and then click **Copy**.
- Step 9 Click Save.

5.3.2.11 PTZ Restart

Restart the PTZ. Follow these steps to complete the configuration.





Step 2 Click **PTZ Restart**. The PTZ is restarted.

5.3.2.12 Default

Restore the PTZ to factory defaults.



This function will restore the Device to defaults. Think twice before performing the operation.

<u>Step 1</u> Select Setting > PTZ > Function > Default.

The **Default** interface is displayed. See Figure 5-77.



Figure 5-77 Default setting



Step 2 Click Default.

The PTZ will be restored to factory defaults.

5.4 Event Management

5.4.1 Video Detection

Video detection includes three event types: Motion Detection, Video Tamper and Scene Changing.

5.4.1.1 Motion Detection

When the moving object appears and moves fast enough to reach the preset sensitivity value, alarms will be triggered.

<u>Step 1</u> Select Setting > Event > Video Detection > Motion Detection.

The Motion Detection interface is displayed. See Figure 5-78.



Figure 5-78 Motion detection settings

Motion Detection	Video Tamper	Scene Changing
Enable		
Period	Setting	
Anti-Dither	5	s (0~100)
Area	Setting	
🗹 Enable Manua	al Con	
Record		
Record Delay	10	s (10~300)
Relay-out	1 2	
Alarm Delay	10	s (10~300)
Send Email		
PTZ		
Snapshot		
	Default	t Refresh Save

<u>Step 2</u> Select the **Enable** check box, and then configure parameters as needed.

- Set arming and disarming period.
- 1) Click **Setting**, and then set the arming and disarming period on the interface. See Figure 5-79.






Figure 5-79 Arming and disarming period settings

 Set the alarm period to enable alarm events in the period you set. There are 6 time periods for each day. Select the check box for the time period to enable it.

Select the day of week (**Sunday** is selected by default; If **All** is selected, the setting is applied to the whole week. You can also select the check box next to the day to set it separately).

3) After completing the settings, click **Save**.

You will return to the Motion Detection interface.

• Set the area.

Click **Setting**, and the **Area** interface is displayed. See Figure 5-80. Refer to Table 5-24 and Table 5-25 for parameters description. Each color represents a certain region, and you can set different motion detection regions for each area. The detection region can be irregular and discontinuous.



Figure 5-80 Area setting

			Region	
			Name Reg	ion1
st#≠ 44 0 P 71.2 T 10.3			Sensitivity 🖃	
			Threshold 🖃 🗍	+ 5
		3		
	t t			_
	elete (Or Rightclin	2000 00 Kg		

Table 5-24 Area setting parameter description

Parameter	Description
Name	The default names are Region1, Region2, Region3 and Region4, and the
name	names can be customized.
	Sensitivity to brightness change. The higher the sensitivity is, the easier the
Sopoitivity	motion detection event will occur.
Sensitivity	You can set different sensitivities for each region, with values ranging from 0
	to 100, and 30 to 70 is recommended.
	Detect the relation between the object and the region. The smaller the
Threshold	threshold is, the easier the motion detection will occur.
Theshold	Set different thresholds for each region, with values ranging from 0 to 100,
	and 1 to 10 is recommended.
Waveform	The red line indicates that motion detection is triggered, and the green line
graph	indicates that it is not triggered.
Remove All	Remove all detection regions.
Delete	Delete the detection region of the selected color block.

Other parameters .

Table 5-25 Video detection parameter description

Parameter	Description
Anti-Dither	The system records only one motion detection event within the defined
	period. The value range is 0–100 s.
Enable	After you enable the function, the motion detection events that occur when
Manual	you control the PTZ manually will be excluded. In this way, you can reduce
Control	the false alarm rate of such events.
Trigger	



Parameter	Description
Record	After you enable the function, when an alarm is triggered, the system will start
	recording automatically. Before using the function, you need to set the
	recording period of the alarm in Storage > Schedule , and select Auto for
	Record Mode on the Record Control interface.
Record	When the alarm is over, the alarm recording will continue for an extended
Delay	period of time. The time unit is second, and the value range is 10–300.
Relay-out	Select the check box, and you can enable the alarm linkage output port, and
	link corresponding relay-out devices after an alarm is triggered.
Alarm Delay	When the alarm is over, the alarm will continue for an extended period of
	time. The time unit is second, and the value range is 10–300.
Send Email	After you select the check box, when an alarm is triggered, the system sends
	email to the specified email address. You can configure the email address in
	"5.2.5 SMTP (Email)."
PTZ	Select PTZ , and then configure the linkage action. When an alarm is
	triggered, the system links PTZ to rotate to the preset. The Activation
	options include None, Preset, Tour and Pattern.
Snapshot	Select the Snapshot check box, and then the system takes snapshot
	automatically when an alarm is triggered. You need to set the alarm snapshot
	period as described in "5.5.1.2 Snapshot."

Step 3 Click Save.

5.4.1.2 Video Tamper

Alarms will be triggered if there is video tampering.

<u>Step 1</u> Select Setting > Event > Video Detection > Video Tamper. The Video Tamper interface is displayed. See Figure 5-81.



Figure 5-81 Video tamper settings

Motion Detection	Video Tamper	Scene Changing
Enable		
Period	Setting	
Record		
Record Delay	10	s (10~300)
Relay-out	1 2	
Alarm Delay	10	s (10~300)
Send Email		
PTZ		
Snapshot		
	Default	Refresh Save

<u>Step 2</u> Select the **Enable** check box, and then configure parameters as needed.

For parameters configuration, see "5.4.1.1 Motion Detection."

Step 3 Click Save.

5.4.1.3 Scene Changing

Alarms will be triggered if there is scene changing.

<u>Step 1</u> Select Setting > Event > Video Detection > Scene Changing. The Scene Changing interface is displayed. See Figure 5-82.



Motion Detection	Video Tamper	Scene Changing	
Enable			
Period	Setting		
Record			
Record Delay	10	s (10~300)	
Relay-out	1 2		
Alarm Delay	10	s (10~300)	
Send Email			
PTZ			
Snapshot			
	Default	Refresh	Save

For parameters configuration, see "5.4.1.1 Motion Detection."

Step 3 Click Save.

5.4.2 Smart Motion Detection

After you set smart motion detection, when the human, non-motor vehicles and motor vehicles appear and move fast enough to reach the preset sensitivity value, the alarm linkage actions will be performed. The function can help you to avoid the alarms triggered by natural environment change.

Ш

- The function depends on the result of motion detection, and all other parameters (except • sensitivity) of motion detection function are used, including arming period, area settings, and linkage configurations. If no motion detection is triggered, smart motion detection will not be triggered.
- If motion detection is not enabled, when smart motion detection is enabled, motion detection will also be enabled. If both functions are enabled, when motion detection is disabled, smart motion detection will also be disabled.
- When smart motion detection is triggered and recording is linked, back-end devices can • filter recording with human or vehicles through smart search function. For details, see the corresponding user's manual.



Preparation

- Select **Setting > Event > Video Detection > Motion Detection**, and then enable the motion detection function.
- Set the arming period and detection area. The sensitivity of each region is larger than 0, and the threshold is not equal to 100.

Procedure

<u>Step 1</u> Select Setting > Event > Smart Motion Detection.

The **Smart Motion Detection** interface is displayed. See Figure 5-83. Figure 5-83 Smart motion detection

Smart Motion Detection			
Enable			
Effective object	Human	Motor Vehicle	
Sensitivity	Medium	~	
	Default	Refresh	Save

<u>Step 2</u> Select the **Enable** check box, and then the **Smart Motion Detection** is enabled.

<u>Step 3</u> Select the effective object and sensitivity.

- Effective object: Select Human or Motor Vehicle. When Human is selected, both people and non-motor vehicles will be detected.
- **Sensitivity**: Select **High**, **Medium**, or **Low**. The higher the sensitivity, the easier the alarm is triggered.
- Step 4 Click Save.

5.4.3 Audio Detection

<u>Step 1</u> Select Setting > Event > Audio Detection > Audio Detection. The Audio Detection interface is displayed. See Figure 5-84.



Figure 5-84 Audio detection settings

idio Detection				
Input Abnormal				
Intensity Change				
Sensitivity	E	0	+ 50	
Threshold		0	+ 50	
In the second				
		-		
Period	Setting			
Anti-Dither	5	s (0~	-100)	
Record				
Record Delay	10	s (10)~300)	
Relay-out	1 2			
Alarm Delay	10	s (10)~300)	
Send Email				
PTZ				
Snapshot				
Default	Refresh		Save	

<u>Step 2</u> Configure parameters as needed. For the parameter description, see Table 5-26.

Table 5-26 Audio detection parameter description	ı
--	---

Parameter	Description
Input	Select Input Abnormal, and then an alarm is triggered when there is
Abnormal	abnormal audio input.
Intensity	Select Intensity Change, and then an alarm is triggered when the change in
Change	sound intensity exceeds the defined threshold.
	The value ranges from 1 to 100. The smaller this value is, the larger the input
Sensitivity	sound volume changes are needed for it to be judged as an audio anomaly.
	You need to adjust it according to the actual condition.
	The value ranges from 1 to 100. Configure the ambient sound intensity you
Threshold	need to filter. The louder the ambient noise is, the larger this value shall be.
	You need to adjust it according to the actual condition.

For other parameters, see "5.4.1.1 Motion Detection."

Step 3 Click Save.



5.4.4 Smart Plan

Smart plans include IVS, face recognition, heat map, people counting, video metadata, and so on. Only after smart plans have been enabled, can the corresponding smart function come into effect.

Before configuring the smart plan, you need to set presets in advance. For setting methods, see "5.3.2.1 Preset."

<u>Step 1</u> Select **Setting > Event > Smart Plan**.

The Smart Plan interface is displayed.

Figure 5-85 Smart plan (1)

*

Step 2 (Optional) Click to enable Auto Tracking.

When enabling auto tracking, you do not need to configure smart plans, and the Device perform auto tracking based on internal mechanism. If auto tracking and alarm track of the smart plan (such as IVS) are both enabled, the Device perform tracking in the order of triggering time.

 \square

It is recommended to disable auto tracking when alarm track is enabled to avoid disordered tracking.

- Step 3 Click Add Plan to select the presets to be configured.
- <u>Step 4</u> Select smart plans as needed.

The selected function will be highlighted. See Figure 5-86. Click it again to cancel the selection.





Step 5 Click Save.

5.4.5 IVS

Basic Requirements for the Scene

- The target size shall not exceed 10% of the image.
- The pixel of the target shall be no less than 10×10; the pixel of abandoned object shall be no less than 15×15 (CIF image); the width and height of the target shall be no more than 1/3 of the image. It is recommended that the height of the target is 10% of the image.
- The brightness difference between the target and the background is no less than 10 gray values.
- The target shall be present in the image for no less than 2 consecutive seconds, and the moving distance shall be larger than its width and no less than 15 pixels (CIF image).
- Try to reduce the complexity of monitoring scenes. It is not recommended to enable IVS in scenes with dense targets and frequent light changes.
- Try to avoid the following scenes: scenes with reflective surfaces such as glass, bright ground or water; scenes that disturbed by tree branches, shadows or winged insects; scenes that against light or under direct light exposure.

Before using the function, you need to set presets in advance. For setting methods, see "5.3.2.1 Preset."

5.4.5.1 Rule Config


Set smart rules. Follow these steps to complete the configuration.

<u>Step 1</u> Select Setting > Event > IVS > Rule Config.

The Rule Config interface is displayed. See Figure 5-87.



Figure 5-87 Adding smart rules



Step 2 Select the presets to be configured with smart rules.

Step 3 Click 🔂 to add smart rules.

Double-click rule type to modify the type of rules.

Step 4 Click Save.

5.4.5.1.1 Tripwire

Alarms are triggered when the target crosses the warning line in the defined direction.

It requires certain stay time and moving space for the target to be confirmed, so you need to leave some space at both sides of the warning line during configuration and do not draw it near obstacles.

Applicable scenes: Scenes with sparse targets and no occlusion between targets, such as perimeter protection of unattended areas.

<u>Step 1</u> Select **Tripwire** from the **Rule Type** list.

The configuration interface is displayed. See Figure 5-88.



Figure 5-88 Tripwire rule settings

		2019-12-03 19:39:30	V No.	Name	-	Rule Type	
* 2411 P.85T 137.2.2	4		1	Rule1		Tripwire	~
a a a a a a a a a a a a a a a a a a a			Paramete	Catura			
r†		- The second	Period		Setting]	
	the star is fare to be				200		
Tz Camera			Directi		A<->B	~	
T2 Camera			Alarm	Track			
T2 Camera		Clear	Alarm	Track Time	A<->B 30	► s (15~300)	1
	8191 * 8191	Clear Draw Target	 ✓ Alarm Track ✓ Object 	Track Time filter		s (15~300)	otor Vehicl
w Rule	8191 * 8191 D * 0		 ✓ Alarm Track ✓ Object 	Track Time filter ve object	30	s (15~300)	
v Rule		Draw Target	 ✓ Alarm Track[™] ✓ Object Effectiv ✓ Record 	Track Time filter ve object	30	s (15~300)	otor Vehicl
v Rule rget filter • Max Size • Min Size	0 * 0	Draw Target Clear Draw Target	 ✓ Alarm Track[™] ✓ Object Effectiv ✓ Record 	Track Time filter ve object d d Delay	30 ☑ Human	s (15~300)	otor Vehicl
v Rule get filter Max Size Min Size el Counter	0 * 0	Draw Target Clear Draw Target	 Alarm Track Object Effectiv Record Record 	Track Time filter ve object d d Delay out	30 ☑ Human 30	s (15~300)	otor Vehicl

- <u>Step 2</u> Click **Draw Rule**, and you can draw rules on the monitoring screen. For parameter description, see Table 5-27.

Click Clear to the right of Draw Rule, and you can clear all drawn rules.

Parameter	Description
Max Size	Set the size range of detection targets to be filtered, and select the maximum
Min Size	 or minimum size. Max Size: Set the maximum size of targets to be filtered. When the target is larger than this size, the system will ignore it. The unit is pixel. Min Size: Set the minimum size of targets to be filtered. When the target is smaller than this size, the system will ignore it. The unit is pixel.
Pixel Counter	Help to accurately draw the target area. Enter the length and width of the target area in Pixel Counter , and click Draw Target to generate the target area in the monitoring screen. The unit is pixel.
Lock/Unlock	Enter the rule configuration interface, and the locking function will be automatically enabled, and the locking time is 180 s. During this period, the device cannot track the target. Click Unlock to release the control.
	The locking function only takes effect in the rule configuration interface. After
	switching to the Live interface, the Device can track the target normally.

Table 5-27 Rule drawing parameter description

<u>Step 3</u> Configure parameters as needed. For the parameter description, see Table 5-28.



	Table 5-28 Tripwire parameter description
Parameter	Description
	Set the alarming period to enable alarm events in the period you set.
	1. Click Setting , and then the Period interface is displayed.
	2. Enter the time value or press and hold the left mouse button, and
	drag directly on the setting interface. There are six periods for
Period	setting each day. Select the check box next to the period, and the
1 onou	set period will be effective.
	3. Select the day of week (Sunday is selected by default; If All is
	selected, the setting is applied to the whole week. You can also
	select the check box next to the day to set it separately).
	4. After completing the setting, click Save to return to the rule
	configuration interface.
Direction	Configure the tripwire direction. You can select A->B , B->A or A<->B .
Alarm Track	Select the check box, and there will be alarm tracking when an smart rule is
	triggered.
Track Time	Set the alarm tracking time.
	Select the check box, and when an alarm is triggered, the system will start
Record	recording automatically. Before using the function, you need to set the
	recording period of the alarm in Storage > Schedule , and select Auto for
	Record Mode in the Record Control interface.
Record	When the alarm is over, the recording will continue for an extended period of
Delay	time. The value range is 10–300 s.
Relay-out	Select the check box, and you can enable the alarm linkage output port, and
	link corresponding relay-out devices when an alarm is triggered.
Alarm Delay	When the alarm is over, the alarm will continue for an extended period of
,	time. The value range is 10–300 s.
. . .	Select the Send Email check box, and when an alarm is triggered, the
Send Email	system sends an email to the specified mailbox. You can configure the
	mailbox in Setting > Network > SMTP (Email).
Snapshot	Select the check box, and the system will automatically take snapshots in
Step 4 Click S	case of alarms. You need to set snapshot period in Storage > Schedule .

Step 4 Click Save.

5.4.5.1.2 Intrusion

Intrusion includes crossing areas and in-area functions.

- Crossing area means an alarm will be triggered when a target enters or leaves the area.
- In-area function means an alarm will be triggered when a specified number of targets appear in a set alarming area at a given time. In-area function only counts the number of targets in the detection area, regardless of whether they are the same targets.
- For the reporting time interval of the in-area functions, the system will trigger the first alarm and then detect whether the same event occurs in the interval period. If no same event occurs in this period, the alarm counter will be cleared.

Similar to the warning line, to detect an entry/exit event, a certain movement space should be reserved at the periphery of the area line.



Rule Config

Applicable scenes: Scenes with sparse targets and no occlusion between targets, such as perimeter protection of unattended areas.

<u>Step 1</u> Select **Intrusion** from the **Rule Type** list.

The configuration interface is displayed. See Figure 5-89.

Figure 5-89 Intrusion settings

	2	019-12-03 19:40:23	~	No.	Name		Rule Type		÷
Press 2				1	Rule1		Tripwire	~	•
Preset3 1 24°C P:8.5 T:13.7 Z.2		L. Links		2	Rule2		Intrusion	~	0
d	- vertexet - Action								
		lle2							1 M
Manual Contractor			Par	ameter	Setup -				
				Period		Setting	1		
C		- ALASTON					1		
FTZ Camera		A. C.		Action		Appears	Cross		
				Alarm	Track				
				Track 1	îme	30	s (15~300)		
raw Rule		Clear		Object	filter				
Target filter Max Size	8191 * 8191	Draw Target		Effectiv	e object	I Human	Mc	tor Vehi	cle
O Min Size	0 * 0	Clear		_					
Pixel Counter	0 * 0	Draw Target	1 mar	Record		30	s (10~300)		
			100	Record		_	s (10~300)		
Tracking Target Siz	() + 25		1000	Relay-0		1 2	s (10~300)		
Lock(180s)			1.2	Alarm I		10	5(10~300)		
				Send E					
			~	Snapsk	ot				

<u>Step 2</u> Click **Draw Rule**, and you can draw rules on the monitoring screen. For parameter description, see Table 5-27.

Click Clear to the right of Draw Rule, and you can clear all drawn rules.

<u>Step 3</u> Configure parameters as needed. For the parameter description, see Table 5-29.

Parameter	Description
Action	Configure intrusion action, and you can select Appear or Cross.
Direction	Select the crossing direction from Enters, Exits, and Enter & Exit.

For other parameters, see "5.4.5.1.1 Tripwire."

Step 4 Click Save.

5.4.5.1.3 Abandoned Object

An alarm will be triggered when the selected target in the monitoring scene stays in the screen for more than the set time.

Pedestrians or vehicles that stay for too long would be regarded as abandoned objects. To filter out such alarms, you can use **Target filter**. In addition, the duration can be properly extended to avoid false alarm due to a short stay of people.



Applicable scenes: Scenes with sparse targets, no obvious and frequent light changes. For scenes with intensive targets or too many obstacles, missed alarms would increase; for scenes in which too many people stay, false alarms would increase. Select detection areas with simple texture, because this function is not applicable to scenes with complex texture.

<u>Step 1</u> Select Abandoned Object from the Rule Type list.

The configuration interface is displayed. See Figure 5-90. Figure 5-90 Abandoned object settings

			Prese	at [3:P	Preset3	~			
434	20	019-12-03 19:42:31	~	No.	Name		Rule Type		-{
2	A 157 11	Contra State	~	1	Rule1	_	Tripwire	~	•
24 C P.20.5 T.12.6 Z.6	Manuel 1	- 10 C		2	Rule2		Intrusion	~	•
		and the second		3	Rule3		Abandoneo	i Ot 🗸	
NEX C		1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1							
Rule3									
			Parar	neter :	Setup				
			Pe	eriod		Setting			
		TABLE .							
Z Camera		- market	Di	Iration		10	ste	6~3600)	
2.2300000						10		, ,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,	
2-35011-10-			✓ AI	arm Ti	rack				
		Class	✓ AI		rack	30	s (15~30		
		Clear	✓ AI	arm Ti ack Ti	rack				
Rule	* 8191	Clear Draw Target	✓ Al Tr	arm Ti ack Ti	rack me			0)	
Rule			✓ Al Tr ✓ Re Re	arm Ti ack Ti ecord ecord I	rack me Delay	30	s (15~30	0)	
get filter Max Size 8191 Min Size 0	* 0	Draw Target Clear	 ✓ Al Tr ✓ Re Re ✓ Re 	arm Ti ack Ti ecord ecord I elay-ou	rack me Delay ut	30 30 1 2	s (15~30	0) 00)	
get filter Max Size 8191 Min Size 0		Draw Target	 ✓ AI Tr ✓ Re Re AI 	arm Ti ack Ti ecord ecord I elay-ou arm D	rack me Delay ut elay	30	s (15~30	0) 00)	
get filter Max Size 8191 Min Size 0	* 0	Draw Target Clear	 ✓ AI Tr ✓ Re Re AI 	arm Ti ack Ti ecord ecord I elay-ou arm D end Er	rack me Delay ut elay nail	30 30 1 2	s (15~30	0) 00)	

<u>Step 2</u> Click **Draw Rule**, and you can draw rules on the monitoring screen. For parameter description, see Table 5-27.

Click Clear to the right of Draw Rule, and you can clear all drawn rules.

<u>Step 3</u> Configure parameters as needed. For the parameter description, see Table 5-30.

Table 5-30 Abandoned object parameter description

Parameter	Description
Duration	For abandoned object, the duration is the shortest time to trigger an alarm
	after an object is abandoned.

For other parameters, see "5.4.5.1.1 Tripwire."

Step 4 Click Save.

5.4.5.1.4 Missing Object

An alarm will be triggered when the selected target in the scene is taken away for the time longer than the set duration.

The system analyzes static areas from the foreground, and determines whether it is missing object or abandoned object from the similarity of its foreground and background. When the time exceeds the set period, an alarm is triggered.



Applicable scenes: Scenes with sparse targets, no obvious and frequent light changes. For scenes with intensive targets or too many obstacles, the missed alarm would increase; for scenes in which too many people stay, the false alarm would increase. Keep the detection area texture as possible simple as possible, because this function is not applicable to scenes with complex texture.

<u>Step 1</u> Select **Missing Object** from the **Rule Type** list.

The configuration interface is displayed. See Figure 5-91. Figure 5-91 Missing object setting

				and a standard standard standard		1000			D.I. T.	
		-	201	19-12-03 19:44:23	~	No.	Name	-	Rule Type	-8
	T:137Z2			and the second	> >	1	Rule1 Rule2		Tripwire V	•
24% F.0.0	1:10/ 2:2	nH T	A anno la		~	3	Rule2		Abandoned Ot V	
		Source and the second			2	4	Rule4		Missing Object V	0
	adianan	nanar ^{ana} .		\geq]	Para	amete	r Setup -			
	•				ł	Period		Setting]	
Z Camera						Period		Setting 10	s (6~3600)	
Z Camera	rt All				I	Duratio			s (6~3600)	
ZCamera			-			Duratio	on Track		s (6~3600)	
				Clear		Duratio Alarm	on Track Time	10		
Z Carnera / Rule get filter	• Max Size	8191 * 8191		Clear Draw Target		Duratio Alarm Frack Recore	on Track Time	10		
Rule	Max Size Min Size					Duratio Alarm Frack Recore	on Track Time 1 1 Delay	10	s (15~300)	
Rule	O Min Size	8191 * 8191 0 * 0		Draw Target Clear		Duratio Alarm Frack Record Record Record	on Track Time 1 1 Delay	10 30 30	s (15~300)	
Rule let filter	O Min Size	8191 * 8191 0 * 0	± 25	Draw Target		Duratio Alarm Frack Record Record Record	on Track Time d d Delay out Delay	10 30 30 1 2	s (15~300) s (10~300)	

<u>Step 2</u> Click **Draw Rule**, and you can draw rules on the monitoring screen. For parameter description, see Table 5-27.

Ш

Click Clear to the right of Draw Rule, and you can clear all drawn rules.

<u>Step 3</u> Configure parameters as needed. For the parameter description, see Table 5-31.

Table 5-31 Missing object parameter description

Parameter	Description
Duration	Configure the shortest time from the object disappearing to the alarm being
	triggered.

For other parameters, see "5.4.5.1.1 Tripwire."

Step 4 Click Save.

5.4.6 Face Recognition

Select Setting > Event > Smart Plan, and then enable face recognition.



• This function is available on select models.

The function can detect faces and compare them with those in the configured face database.

5.4.6.1 Face Detection

When human face is detected in the monitoring screen, an alarm is triggered and the linked activity is executed.

<u>Step 1</u> Select Setting > Event > Face Recognition > Face Detection.

The **Face Detection** interface is displayed. See Figure 5-92.

Figure 5-92 Face detection interface



<u>Step 2</u> Select **Enable**, and you can enable the face detection function.

<u>Step 3</u> Configure parameters as needed. For the parameter description, see Table 5-32.

Parameter	Description							
Period	Alarm event will be triggered only within the defined time period. See							
Fellou	"5.4.1.1 Motion Detection."							
Face	Select Face Enhancement to preferably guarantee clear faces with low							
Enhancement	stream.							
	Select Record , and the system records video when alarms are triggered.							
	To enable video recording, you need to make sure that:							
Record	• The motion detection recording is enabled. For details, see "5.5.1.1							
	Record."							
	• The auto recording is enabled. For details, see "5.5.4 Record							
	Control."							
Record Dolov	The video recording will not stop until the record delay time you set has							
Record Delay	passed.							

Table 5-32 Face detection parameter description



Parameter	Description					
	Select Send Email, and when alarms are triggered, the system sends					
Send Email	email to the specified mailbox. For the email settings, see "5.2.5 SMTP					
	(Email)."					
	Select Snapshot, and the system takes snapshot when alarms are					
	triggered.					
Snapshot						
Shapshot	• Enable the motion detection snapshot first. For details, see "5.5.1.1					
	Record."					
	• For searching and setting snapshot storage path, see "5.1.2.5 Path."					
Snap Face	Set the energy bet seens, including Face and One inch photo					
Image	Set the snapshot scope, including Face and One-inch photo .					
Attribute	Select the Attribute check box, click 🔯, and then you can set the human					
Aundule	attributes during face detection.					

Step 4 Click Save.

5.4.6.2 Face Database Config

After you successfully configure the face database, the detected faces can be compared with the information in the face database. Configuring a face database includes creating a face database, adding face pictures, and face modeling.

5.4.6.2.1 Adding Face Database

Create a face database, and then register face images, that is to add face pictures to the newly created face database.

<u>Step 1</u> Select Setting > Event > Face Recognition > Face Database Config.


The **Face Database Config** interface is displayed. See Figure 5-93.

Figure 5-93 Face database config

	Face Database	Register No	Depity	Similarity Threshold	Moretnio	Arm/Disarm	Delete
	t	93		82		0	•
2	dh	4670	2	82	-		

<u>Step 2</u> Click Add Face Database.

The **Add Face Database** interface is displayed. See Figure 5-94.



Add Face Da	tabase		
Name			
Γ	ок	Cancel	

<u>Step 3</u> Set face database name.

<u>Step 4</u> Click **OK** to complete the addition.



The added face database is displayed. See Figure 5-95. Figure 5-95 Adding face database completed

	Face Database	Register No	Deploy 🔤	Somardy Threshold			
r	1	93		82		ġ.	٠
2	dh	4670	50	82	13	191	

<u>Step 5</u> Configure parameters as needed. For the parameter description, see Table 5-33.

Parameter	Description
Deploy	Select Deploy and the face database takes effect.
	The comparison is successful only when the similarity between the
Similarity	detected face and the face feature in face database reaches the set
Threshold	similarity threshold. After this, the comparison result is displayed on the
	Live interface.
Moro Info	Click More Info to manage face database. You can set search conditions,
More Info	register people, and modify people information.
Arm (Dis arm	Alarm event will be triggered only within the defined time period. See
Arm/Disarm	"5.4.1.1 Motion Detection."
Delete	Delete the selected face database.

Table 5-33 Face database config parameter description

5.4.6.2.2 Adding Face Pictures

Add face pictures to the created face database. Manual addition and batch import are supported.

Manual Addition

Add a single face picture. Use this method when registering a small number of face pictures.

<u>Step 1</u> Select Setting > Event > Face Recognition > Face Database Config.

The Face Database Config interface is displayed.

Step 2 Click III More Info for the face database to be configured.

The interface is displayed. See Figure 5-96.

Figure 5-96 More info

Face Detection Face Database Config Alarm	
Back Face Database: 1	Task List
Name Gender Unlimited V Date of Birth yyyy-mm-d Te Modeling Status Unlimited V	
Credentials Ty Unlimited V ID No. Region Unlimited V Search	
Registration Batch Registration Modeling All Modeling	🖾 Add to the delete list 📃 🗈

Set filtering conditions as needed, and then click **Search**. The search result is displayed.

Step 3 Click Registration.

The **Registration** interface is displayed. See Figure 5-97.



Figure 5-97 Registration interface

Registration	1			×
Upload Pictur	e			
Name* Gender Date of Birth Region City	Male yyyy-mm-dd Unlimited Customized	> = > >	Upload Picture	
Credentials ID No. Address Merno		~		
			Add to task list Cancel	

Step 4 Click Upload Picture.

Import the face pictures to be uploaded. The interface is displayed. See Figure 5-98.

You can manually select a face area. After uploading the picture, select a face area and click **OK**. If there are multiple faces in a picture, select the target face and click **OK** to save the face picture.



Figure 5-98 Addition completed

Registration	1		L. L
Upload Picture			OK Cancel
Name* Gender Date of Birth	Male yyyy-mm-dd	~	
Region City	Unlimited Customized	~	
Credentials ID No. Address		~	
Memo			Add to task list Cancel

- <u>Step 5</u> Fill in face picture information as needed.
- Step 6 Click Add to task list.

Step 7 Click Task List 1

The **Task List** interface is displayed. See Figure 5-99.

Figure 5-99 Task list addition completed

Task List		
Add	Status	~
1	Stored successfully., Modeling failed.:4(Picture Decoding Error)	
Modify	Status	
Delete	Status	
m	OK Remove All	

Click Remove All, and you can remove all the tasks.

Batch Registration

Import multiple face pictures in batch. Use this method when registering a large number of face pictures.

Before importing pictures in batches, name the face pictures in the format of "Name#SGender#BDate of Birth#NRegion#TCredentials Type#MID No. jpg" (for example, "John#S1#B1990-01-01#NCN#T1#M330501199001016222"). For naming rules, see Table 5-34.

Name is required and the rest are optional.

Table 5-34 Naming rules for batch import

Naming Rules	Description
Name	Enter the corresponding name.
Gender	Enter a number. 1: Male; 2: Female.
Date of Birth	Enter numbers in the format of yyyy-mm-dd. For example, 2017-11-23.
Region	Enter the region name.
Credentials	Enter e number 1. ID cards 2. necessart
Туре	Enter a number. 1: ID card; 2: passport.
ID No.	Enter ID No.

<u>Step 1</u> Select Setting > Event > Face Recognition > Face Database Config.

The Face Database Config interface is displayed.

Step 2 Click I More Info for the face database to be configured.

The Face Database interface is displayed.

- Step 3 Click Batch Registration.
 - The **Task List** interface is displayed. See Figure 5-100.

Figure 5-100 Batch registration

Task List			×
		+ Supported Picture Format(.jpg)	
Example: J Gender:1.N	ohn#S1#B1990 Iale 2.Female	Gender#BDate of Birth#NRegion#TCredentials Type#MID No. 0-01-01#NCN#T1#M330501199001016222 assport 3. 4.Other	
		Browse Cancel	
Step 4 Click	+ to sel	ect the file path.	
		Figure 5-101 Batch registration	
Task List			×
Path:	D:\		
File Size:	28		
		Browse Cancel	

Step 5 Click Browse.

The registering interface is displayed. See Figure 5-101.



Figure 5-102 Registering

Task List		×
	Registering faces in batch, please wait12%	
	Check Details Cancel	

<u>Step 6</u> After the registration is completed, click **Next** to view the registration result.

5.4.6.2.3 Managing Face Pictures

Add face pictures to face database; manage and maintain face pictures to ensure correct information.

Modifying Face Information

On the Face Database Config interface, move the mouse pointer to the face picture or person

information line. Click Z or Z, and the **Registration** interface is displayed. See Figure

5-103. After modifying the face picture information as needed, click **Add to task list**. Figure 5-103 Registration interface

Registration	1			X
Upload Pictur				
Name*	1000		Upload Picture	
Gender		~		
Date of Birth	yyyy-mm-dd			
Region	Unlimited	~		
City	Customized	~		
Credentials	Other	~		
ID No.				
Address				
Memo				
			Add to task list Cancel	

Deleting Face Pictures

Enter face database, and then delete the created face picture.

• Single deletion: Move the mouse pointer to the face picture or people information line, and

then click \square or \square to delete the face picture.



- Batch deletion: Move the mouse pointer to the face picture or people information line, and then click at the upper right corner of the face pictures, or click on person information line. After selecting multiple items, click Add to the delete list, click
 Task List 1, and then click OK to delete the selected face pictures.
- Delete all: When viewing face pictures in a list, click on people information line (or select **All** when viewing face pictures in pictures), click **Add to the delete list**, click

Task List 1, and then click **OK** to delete all face pictures.

5.4.6.2.4 Face Modeling

Extract and import the relevant information of face pictures into the database through face modeling, and create a face feature mode for smart detection such as face comparison.

- The more face pictures you choose, the longer the modeling time is. Wait patiently.
- During the modeling process, some smart detection functions (such as face comparison) are temporarily unavailable and can be resumed after the modeling is completed.
- <u>Step 1</u> Select Setting > Event > Face Recognition > Face Database Config. The Face Database Config interface is displayed.

Step 2 Click III More Info for the face database to be configured.

The face database interface is displayed. See Figure 5-104. Figure 5-104 Face database interface

Each Face Database. dt	Task List
Name Debider Unlimited ✓ Date of Barty yyyy emed ™ Yyyy emed ™ Modeling Status Unlimited ✓ Credentass Ty, Unlimited 00 No. Region Unlimited Search	
Registration Batch Registration Modeling All Modeling	Add to the delete list 🔢 🔝

<u>Step 3</u> Choose the face pictures for modeling as needed.

Click 🔳 to view the face picture in a list. Click 🔼 to view the face image as a thumbnail.

a Madaling

- Modeling All
- Click Modeling All, and all face pictures in the face database will be modeled.
- Selective Modeling

If there are many face pictures in the face database, set filtering conditions and click **Search** to select face pictures for modeling.



Figure 5-105 Modeling completed

Task List		E
	Modeling completed.	
Success:0		
E Failure: 0 Search		

5.4.6.3 Alarm Linkage

Set the alarm linkage mode for face comparison.

<u>Step 1</u> Select Setting > Event > Face Recognition > Alarm.

The **Alarm** interface is displayed. See Figure 5-106.

Figure 5-106 Alarm linkage

Face Detection	Face Database Config Alarm
Face Database	1 ~
Relay-out	Alarm Channel1 V
Alarm Rule	✓ Face Recognition Succeeded ✓ Face Recognition Failed
Alarm Delay	1 Sec. (1~300)
	Refresh Save

<u>Step 2</u> Configure parameters as needed. For the parameter description, see Table 5-35.

Parameter	Description
Face	Select the face database to be configured with alarm linkage.
Database	Select the face database to be configured with alarm linkage.
Alarm Rule	Select the alarm rule as needed.
Relay-out	Select the Relay-out check box, and when an alarm is triggered, the system
	interacts with the linked alarm devices.
Alarm Delay	The alarm will continue for an extended period of time. The value range is 1-
	300 s.

Step 3 Click Save.



5.4.7 People Counting

- Before using this function, you need to enable **People Counting** in **Smart Plan**.
- The people counting data will be overwritten if the disk is full. Back up the data in time as needed.
- This function is available on select models.

You can use this function to count the number of people in the area and generate reports.

5.4.7.1 People Counting

With the function, the system can count the number of people appearing in the monitoring screen within a certain period of time.

<u>Step 1</u> Select Setting > Event > People Counting > People Counting.

The **People Counting** interface is displayed. See Figure 5-107.

Figure 5-107 People counting settings

		Preset Pre	-	~	-
	2019-11-25-20:35:06	✓ No.	Name	Rule Type	÷
	2010-11-2020.00.00	✓ 1	Rule3	People Counting	× •
45°C P-215 517 50 2 4					
		- Parameter : OSD	Setup	Clear	
9	6	000		Ciedi	
	A	Period		Setting	
		Flowrate	Alarm		
		Enter N		0	
		Leave N		0	
Draw Rule	Clear	Strande		0	-
Draw Line	Clear	Suanue	u 140.	U	
		Record			
		Record	Delay	10 s (10~3	00)
		Send Er	nail		
		D PTZ			
		Snapshi	ot		
		- Global Setu	ip —		
		Sensitiv	ity	e	+ 7
		Default	Refi	resh Save	7

- <u>Step 2</u> Select the presets to be configured.
- <u>Step 3</u> Click **Draw Rule**, and you can draw rules on the monitoring screen. For parameter description, see Table 5-27.

Click Clear to the right of Draw Rule, and you can clear all drawn rules.

<u>Step 4</u> Configure parameters as needed. For the parameter description, see Table 5-36.



Table 5-36 People counting parameter description

Parameter	Description				
OSD	Display the number of people displayed in the area in real time. Click Clear ,				
030	and the current number will be zero.				
Enter No.	Set the Enter No., and when the number of people entering reaches the set				
Enter No.	value, an alarm will be triggered.				
	Set the Leave No. , and when the number of people leaving reaches the set				
Leave No.	value, an alarm will be triggered.				
Stranded	Set the Stranded No. , and when the number of people staying reaches the				
No.	set value, an alarm will be triggered.				

For other parameters, refer to "5.4.5.1.1 Tripwire."

Step 5 Click Save.

5.4.7.2 Report

You can view the statistics results of people in the scene during the selected period.

<u>Step 1</u> Select Setting > Event > People Counting > Report.

The **Report** interface is displayed. See Figure 5-108.

Figure 5-108 People counting-report

nge (Datky	
2019-11-25 00:00:00 ~ 2019-11-25 20:00:00 Rule3 People Counting	e Demok 🐞 Evinst
	1

<u>Step 2</u> Select a preset.

<u>Step 3</u> Select the **Rule**, **Statistics Type**, and **Time Range**.

<u>Step 4</u> Select the start time and end time for searching reports.

<u>Step 5</u> Select Flow Direction and Chart Type.

<u>Step 6</u> Click **Search** to generate reports, and click **Export** to export the report to local storage.

5.4.8 Heat Map

- Before enabling **Heat Map**, you need to set presets in **PTZ** section, and select the function in the **Smart Plan**.
- The data will be overwritten if the disk is full. Back up the data in time as needed.



This function is available on select models.


5.4.8.1 Heat Map

The function can be used to detect the activity level of moving objects in the scene during a certain period of time.

<u>Step 1</u> Select Setting > Event > Heat Map > Heat Map.

The Heat Map interface is displayed. See Figure 5-109.

Figure 5-109 Heat map interface



- <u>Step 2</u> Select the presets to be configured.
- <u>Step 3</u> Select the **Enable** check box, and then the heat map function is enabled.
- Step 4 Click Setting to set the arming period. For details, see "5.4.1.1 Motion Detection."
- Step 5 Click Save.

5.4.8.2 Report

You can view the heat map report for the scene in the selected time period.

<u>Step 1</u> Select Setting > Event > Heat Map > Report.

The **Report** interface is displayed.

- <u>Step 2</u> Set the start time and end time to search for the heat map report.
- <u>Step 3</u> Select a preset.
- <u>Step 4</u> Click **Search**, and the search results will be displayed on the interface. See Figure 5-110.



Figure 5-110 Report Heat Map Report Start Time 2019-11-01 00 End Time 2019-11-06 00 00 16 : 00 00 *Report max range is 1 week. Preset 1:Preset1 V Export Search 2019-11-01 00:00:00 ~ 2019-11-06 16:00:00 Heat Map Statistics -07_16:07:49 2019-1 Preset1 2:0.0 T:45.0 Z:1.0 ALLENGER FOR FULLEN IP PTZ Camera

5.4.9 Video Metadata

With the function, the system can count the number of motor vehicles, non-motor vehicles and people in the monitoring screen, identify the features of the vehicles and people in the scene, and take snapshots.

- Before using video metadata, you need to enable the function in the Smart Plan.
- This function is available on select models.

5.4.9.1 Scene Setting

Set the parameters of snapshot, analysis and alarm in the scene.

<u>Step 1</u> Select Setting > Event > Video Metadata.

The Scene Set interface is displayed. See Figure 5-111.



Figure 5-111 Video metadata-scene set

Scene Set Picture	Report						
			Preset	Preset3	~		
	1		~	No.	Name	Rule Type	÷
		2019-12-03 20:20:12		1	Rule2	People V	0
† 24℃ P.8.5 T:13.7 Z:2				2	Rule3	Non-motor V	•
	a a a a a a a a a a a a a a a a a a a		V	3	Rule4	Motor Vehic 🗸	0
i i managerrander managerrander	W. The	i		ter Setup -	at		
		1			Clear		
TZ Qamera		-4	Perio		Setting		
Detect Region Draw		Clear		o Mode ture Compl	ete Vehicle		
Exclude Re. Draw Modify]	Clear		y-out n Delay	1 2 10	s (10~300)	
arget filter Max Size 8191 Min Size 0	* 8191	Draw Target	Defa	ult	Refresh	Save	
ixel Counter 0	* 0	Draw Target					
Zoom	• •	ave Preset					
eed 5 V	(+)						

<u>Step 2</u> Click the **Preset** list to select the preset to configure video metadata.

<u>Step 3</u> Click 🔛 to add a rule type.

<u>Step 4</u> Modify the parameters as needed.

- Double-click the name to modify the rule name.
- Select the rule type from **People**, **Non-motor Vehicle** and **Motor Vehicle**.

Click the corresponding 😑 to delete detection items.

<u>Step 5</u> Configure parameters as needed. For parameter description, see Table 5-37.

Parameter	Description
People Flow	
Statistics	
Non-motor	
Vehicle Flow	After selection, traffic flow statistics will be displayed on the screen.
Statistics	
Traffic Flow	
Statistics	
OSD	Select the check box to enable the OSD overlay. The statistics will be
	displayed on the Live interface in the form of OSD information.
Clear	Click it to clear the statistics of motor vehicles, non-motor vehicles and
Clear	people.

For other parameters, see "5.4.5.1.1 Tripwire."



Step 6 Click Save.

5.4.9.2 Picture Overlay

Set the overlay information on the snapshot.

- <u>Step 1</u> Select Setting > Event > Video Metadata > Overlay. The Picture interface is displayed.
- <u>Step 2</u> Select Picture Overlay Type from People, Non-motor Vehicle and Motor Vehicle.

See Figure 5-112, Figure 5-113 and Figure 5-114.

Figure 5-112 Picture overlay-motor vehicle

Scene Set	Picture	Report					
Time Loca	ation			Picture Overlay — Type	Motor Vehic	cle 🗸	
R		2019-12-	en en este	 Time Location 			
† 23℃ P.8.5 T.13 d 2	1722			Upload Picture	Vehicle Bo	ody Pic	
d	Manufactures.	Mar -		Default	Refresh	Save	
TPFTZ Camera	rt 1		Nie				

Figure 5-113 Picture overlay-non-motor vehicle

Time Location		Picture Overlay Type	Non-motor	Vehicle 🗸
	2019-12-03 20:26:10	Time		
+ 23% P.85T 137Z2	A STATE	Upload Picture	Vehicle E	Body Pic
	A CAR	Default	Refresh	Save
+ +	1. P.			



Figure 5-114 Picture overlay-people

Time Location		Picture Overlay-		
		Туре	People	~
		✓ Time		
	2019-12-03			
1 231 P85T 137Z2		Upload Picture	Vehicle Body F	Pic., .
Mileanolatora a	West .	Default	Refresh	Save
annua.				
T		* Sector		
- ALTER MONT	Sec. Sec.	Letter .		

<u>Step 3</u> Select overlay information as needed.

If you select Location, you need to manually enter the location of the Device.

Step 4 Click Save.

5.4.9.3 Report


You can view the number of vehicles, non-vehicles and people in the scene during the selected period.

Step 1 Select Setting > Event > Video Metadata > Report.

The **Report** interface is displayed.

- <u>Step 2</u> Select the **Report Type**.
- <u>Step 3</u> Select the start time and end time for searching reports.
- <u>Step 4</u> Select the Traffic Flow Statistics Type.
- Step 5 Click Search to generate reports. See Figure 5-115.

Figure 5-115 Video metadata report





5.4.10 Alarm

<u>Step 1</u> Select **Setting > Event > Alarm**.

The **Alarm** interface is displayed. See Figure 5-116.

Liauro	E 1	16	۸I.	rm
Figure	J-1	10	Ala	

Enable					
Relay-in	Alarm1	~]		
Period	Setting				
Anti-Dither	0	s (0~100)	Sensor Type	NO	~
Record					
Record Delay	10	s (10~300)			
Relay-out	1 2				
Alarm Delay	10	s (10~300)			
Send Email					
] PTZ					
Snapshot					

Step 2 Configure parameters as needed. For parameter description, see Table 5-38.

Parameter	Description
Enable	Select the Enable check box, and then the alarm linkage is enabled.
Relay-in	Select alarm input, and 7 alarm inputs are available.
	There are two types: NO (normally open) and NC (normally closed). Switch
Sensor Type	from NO to NC , and alarm event will be enabled. Switch from NC to NO , and
	alarm event will be disabled.
\square	

Table 5-38 Alarm setting parameter description

For other parameters, see "5.4.1.1 Motion Detection."

Step 3 Click Save.

5.4.11 Abnormality

Abnormality includes 7 alarm events: No SD Card, Capacity Warning, SD Card Error, Disconnection, IP Conflict, Illegal Access, and Security Exception.



5.4.11.1 SD Card

In case of an SD card exception, an alarm will be triggered. Follow these steps to complete the configuration.

<u>Step 1</u> Select Setting > Event > Abnormality > SD Card.

The **SD Card** interface is displayed. See Figure 5-117, Figure 5-118, and Figure 5-119. Figure 5-117 No SD card

SD Card	Network	Illegal Access	Security Exception
Event Type	No SD Card	~	
	No 3D Card	`	
Enable			
🖌 Relay-out	1 2		
Alarm Delay	10	s (10~300)	
Send Email			
	Default	Refresh	Save
	Figure 5-118	SD card error	
SD Card	Network	Illegal Access	Security Exception
Event Type	SD Card Erro	or 🗸	
Enable			
✓ Relay-out	1 2		
Alarm Delay	10	s (10~300)	
Send Email			
	Default	Refresh	Save

Figure 5-119 Capacity warning

SD Card	Network	Illegal Access	Security Exception
Event Type	Capacity Wa	arning 🗸	
Enable			
Capacity Limit	10	%(0~99)	
Relay-out	1 2		
Alarm Delay	10	s (10~300)	
Send Email			
	Default	Refresh	Save

<u>Step 2</u> Configure parameters as needed. For parameter description, see Table 5-39.

Table 5-39	SD card	exception	parameter	description

Parameter	Description
Enable	Select the check box to enable this function.
Capacity	Configure the free space percentage, and if the free space in the SD card is
Limit	less than the defined percentage, an alarm is triggered.

For other parameters, see "5.4.1.1 Motion Detection."

Step 3 Click Save.

5.4.11.2 Network Exception

In case of a network exception, an alarm will be triggered. Follow these steps to complete the configuration.

<u>Step 1</u> Select **Setting > Event > Abnormality > Network**.

The Network interface is displayed. See Figure 5-120 and Figure 5-121.

Figure 5-120 Disconnection					
SD Card	Network	Illegal Access	Security Exception		
Event Type	Disconnectio	on 🗸			
Enable					
Record					
Record Delay	10	s (10~300)			
Relay-out	1 2				
Alarm Delay	10	s (10~300)			
	Default	Refresh	Save		
	Derudit				
	Figure 5-1	21 IP conflict			
	0				
SD Card	Network	Illegal Access	Security Exception		
	Network	Illegal Access	Security Exception		
SD Card Event Type	•	Illegal Access	Security Exception		
	Network	Illegal Access	Security Exception		
Event Type	Network	Illegal Access	Security Exception		
Event Type Enable	Network	Illegal Access s (10~300)	Security Exception		
Event Type Enable Record	Network	~	Security Exception		
Event Type Enable Record Record Delay 	Network IP Conflict	~	Security Exception		

<u>Step 2</u> Configure parameters as needed. See Table 5-40.

Table 5-40 Network exception parameter description

Parameter	Description
Enable	Select the check box to enable this function.
Con oth	en never et au 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1

For other parameters, see "5.4.1.1 Motion Detection."

Step 3 Click Save.

5.4.11.3 Illegal Access

Illegal access alarm is triggered when the login password has been wrongly entered for more than the times you set.

<u>Step 1</u> Select Setting > Event > Abnormality > Illegal Access.

The **Illegal Access** interface is displayed. See Figure 5-122.



	Figure 5-122	Illegal access	
SD Card	Network	Illegal Access	Security Exception
Enable			
Login Error	5	time (3~10)	
Relay-out	1 2		
Alarm Delay	10	s (10~300)	
Send Email			
	Default	Refresh	Save

<u>Step 2</u> Configure parameters as needed. For parameter description, see Table 5-41.

Table 5-41 Illegal access parameter description

Parameter	Description
Enable	Select the check box to set the illegal access alarm.
Login Error	After entering a wrong password for the set times, the alarm for illegal access
	will be triggered, and the account will be locked.
	·

For other parameters, see "5.4.1.1 Motion Detection."

Step 3 Click Save.

5.4.11.4 Security Exception

When an event affecting the Device safety occurs, an alarm for safety exception will be triggered.

```
<u>Step 1</u> Select Setting > Event > Abnormality > Security Exception.
```

The Security Exception interface is displayed. See Figure 5-123.

Figure 5-123 Security exception

SD Card	Network	Illegal Access	Security Exception
Enable			
Relay-out	1 2		
Alarm Delay	10	s (10~300)	
Send Email			
	Default	t Refresh	Save

<u>Step 2</u> Configure each parameter as needed. For details, refer to "5.4.1.1 Motion Detection." <u>Step 3</u> Click **Save**.



5.5 Storage

5.5.1 Schedule


Before setting the schedule, make sure that the **Record Mode** is **Auto** in **Record Control**.

If the **Record Mode** is **Off**, the Device will not record or take snapshots according to the schedule.

5.5.1.1 Record

<u>Step 1</u> Select Setting > Storage > Schedule > Record.

The **Record** interface is displayed. See Figure 5-124.



- <u>Step 2</u> Select the day for recording from Monday to Sunday. Click **Setting** on the right, and the **Setting** interface is displayed. See Figure 5-125.
 - Set the recording period as needed. You can set up to six periods for one day.
 - You can select 3 types of recording: **General**, **Motion** and **Alarm**.

To set the time period, you can also press and hold the left mouse button and drag directly on the **Record** interface.




Figure 5-125 Record schedule setting

	🗹 Sun 🗌 Mon 🗌 Tue 🗌 Wed 🗌 Thu 📄 Fri 📄 Sat 🗌 Holiday	
Period1	00 : 00 : 00 - 23 : 59 : 59 General 🗹 Motion 🗹 Alarm	
Period2	00 : 00 : 00 - 23 : 59 : 59 General Motion Alarm	
Period3	00 : 00 : 00 - 23 : 59 : 59 General Motion Alarm	
Period4	00 : 00 : 00 - 23 : 59 : 59 General Motion Alarm	
Period5	00 : 00 : 00 - 23 : 59 : 59 General Motion Alarm	
Period6	00 : 00 : 00 - 23 : 59 : 59 General Motion Alarm	

At this time, the colored chart visually displays the set time period.

- Green: Represents general recording.
- Yellow: Represents motion detection recording.
- Red: Represents the alarm recording.

Figure 5-126 Recording schedule setting completed




<u>Step 4</u> On the **Record** interface, click **Save**, and the **Save Succeeded!** prompt will be displayed, which means the recording schedule has been set.

5.5.1.2 Snapshot

```
<u>Step 1</u> Select Setting > Storage > Schedule > Snapshot.
The Snapshot interface is displayed. See Figure 5-127.
```



Figure 5-127 Snapshot



<u>Step 2</u> For the snapshot schedule settings, refer to Step 2 and Step 3 in "5.5.1.1 Record."

<u>Step 3</u> Click **Save**, and the **Save Succeeded!** prompt will be displayed, which means the snapshot schedule has been set.

5.5.1.3 Holiday Schedule

You can set specific dates as holidays.

<u>Step 1</u> Select Setting > Storage > Schedule > Holiday Schedule. The Holiday Schedule interface is displayed. See Figure 5-128.



Calenda	r				Dec	~
Sun	Mon	Tue	Wen	Thu	Fri	Sat
1	2	3	4	5	6	7
8	9	10	11	12	13	14
15	16	17	18	19	20	21
22	23	24	25	26	27	28
29	30	31				

Step 2 Select a date.

The selected date will be a holiday and displayed in yellow.

- <u>Step 3</u> Select **Record** or **Snapshot**, and then click **Save**. The **Save Succeeded!** prompt will be displayed.
- <u>Step 4</u> On the **Record** or **Snapshot** interface, click **Setting** to the right of **Holiday**. The setting method is the same as that of Monday to Sunday.
- <u>Step 5</u> Set the time period of one day for the **Holiday**, and the recording or snapshot will be taken according to the holiday time period.

5.5.2 Snapshot by Location

The system can take snapshots when the Device rotates to certain presets.

You need to set presets in advance.

<u>Step 1</u> Select Setting > Storage > Snapshot by Location.

The Snapshot by Location interface is displayed. See Figure 5-129.



Figure 5-129 Snapshot by location

Preset	Preset Title	Snapshot -
1	Preset1	
2	Preset2	

Step 2 Select presets.

- Enable snapshot by location.
 - ♦ Click I to enable the function for the corresponding preset.
 - Click Snapshot, and then select All Enabled to enable the function for all presets.
- Disable snapshot by location.
 - ♦ Click **C** to disable the function for the corresponding preset.
 - Click Snapshot, and then select All Disabled to disable the function for all presets.

Step 3 Click Save.

5.5.3 Destination

5.5.3.1 Path

Configure the storage path of recordings and snapshots of the Device, and select local SD card, FTP and NAS for storage. Store recordings and snapshots according to the event type, respectively corresponding to **General**, **Motion** and **Alarm** in the schedule, and then select the corresponding type of recordings or snapshots for storage.

<u>Step 1</u> Select Setting > Storage > Destination > Path.



The **Path** interface is displayed, see Figure 5-130.

Figure	5-130	Path	settings
rigaro	0 100		ootango

ord				Snapshot			
Event Type	Scheduled	Motion Detection	Alarm	Event Type	Scheduled	Motion Detection	Alarm
Local	1	2	1	Local	2	2	•
FTP				FTP			
NAS				NAS			

<u>Step 2</u> Select the corresponding event type and storage method as needed. For details, refer to Table 5-42.

Parameter	Description
Event Type	Select Scheduled, Motion Detection or Alarm.
Local	Save recordings or snapshots to the SD card.
FTP	Save recordings or snapshots to the FTP server.
NAS	Save recordings or snapshots to the NAS server.

Table 5-42 Path parameter description

Step 3 Click Save.

5.5.3.2 Local

Display the SD card information. You can set it as read only or read & write; you can also hot swap or refresh it.

Select **Setting > Storage > Destination > Local**, and the **Local** interface is displayed. See Figure 5-131.

 Path
 Local
 FTP
 NAS

 Name
 Status
 Attribute
 Used Capacity/Total Capacity
 Attribute

 Read Only
 Read & Write
 Hot Swap
 Refresh
 Format

Figure 5-131 Local storage

- Click **Read Only**, and the SD card is set to read only.
- Click Read & Write, and the SD card is set to read & write.
- Click Hot Swap to remove the SD card.
- Click **Refresh** to start formatting the SD card.

After the SD card is formatted, the data will be cleared. Think twice before performing the operation.

5.5.3.3 FTP

FTP function can be enabled only when it is selected as a destination path. When the network is disconnected or does not work, you can save recordings and snapshots to the SD card by using **Emergency (Local)** function.

<u>Step 1</u> Select Setting > Storage > Destination > FTP.



The **FTP** interface is displayed. See Figure 5-132.

Figure 5-132 FTP settings

Path	Local	FTP	NAS	
Enable	SFTP(Recommended)	 Image: A start of the start of		
Server Address	0.0.0.0			
Port	22	(0~65535)		
Username	anonymity			
Password	•••••	••		
Remote Directory	share			
Emergency (Local)				
	test			
	Default	Refresh S	ave	

<u>Step 2</u> Select the **Enable** check box, and the FTP function is enabled.

- There might be risks if the FTP function is enabled. Think twice before enabling the function.
- SFTP is recommended to ensure network security.

<u>Step 3</u> Configure parameters as needed. For parameter description, see Table 5-43.

Parameter	Description
Server Address	The IP address of the FTP server.
Port	The port number of the FTP server.
Username	The username to log in to the FTP server.
Password	The password to log in to the FTP server.
Remote	The destinction path on the ETD conver
Directory	The destination path on the FTP server.
Emergency	If you enable the function, in case of FTP storage exception, the
(Local)	recordings and snapshots will be stored on the local SD card.

Table 5-43 FTP parameter description

<u>Step 4</u> Click **test** to verify the username and password, and test whether FTP is connected to the Device.

Step 5 Click Save.

5.5.3.4 NAS

This function can be enabled only when NAS is selected as a destination path. Select NAS to store files on the NAS server.

<u>Step 1</u> Select Setting > Storage > Destination > NAS.

The NAS interface is displayed. See Figure 5-133.



Figure 5-133 NAS settings

Path	Local	FTP	NAS
Enable	NFS	~	
Server Address	0.0.0.0		
Remote Directory			
	Default	Refresh	ave

Step 2 Configure parameters as needed. For parameter description, see Table 5-44.

Table 5-44 NAS parameter description

Description	
Select the check box to enable NAS function. Select NFS or SMB	
function.	
There might be risks if NFS or SMB is enabled. Think twice before	
enabling the function.	
The IP address of the NAS server.	
The destination with an the NAC server	
The destination path on the NAS server.	

Step 3 Click Save.

5.5.4 Record Control

<u>Step 1</u> Select Setting > Storage > Record Control.

The **Record Control** interface is displayed. See Figure 5-134.

Figure 5-134 Record control

Record Control	
Pack Duration	30 Min. (1~120)
Pre-event Record	5 s (0~5)
Disk Full	Overwrite 🗸
Record Mode	● Auto ○ Manual ○ Off
Record Stream	Main Stream
	Default Refresh Save

Step 2 Configure parameters as needed. For parameter description, see Table 5-45.



	Table 5-45 Record control parameter description
Parameter	Description
Pack Duration	Set the pack duration of each recording file. It is 30 minutes by default.
Pre-event	Set the pre-recording time. For example, if you enter 5, when an alarm is
Record	triggered, the system reads the recording of the first 5 seconds in memory,
	and then records it into a file.
	If alarm recording or motion detection recording occurs, if there is no
	recording before, the video data within N seconds before the recording is
	started will also be recorded into the video file.
Disk Full	You can select Stop or Overwrite .
	• Stop : The system stops recording when the disk is full.
	• Overwrite : The system overwrites the oldest files and keeps
	recording when the disk is full.
	The data will be overwritten if the disk is full. Back up the file in time as
	needed.
Record Mode	You can select Auto, Manual or Off. Select Manual mode to start
	recording immediately, and select Auto mode to record within the
	schedule.
Record Stream	Select Main Stream or Sub Stream.

Table 5-45 Record control parameter description

Step 3 Click Save.

5.6 System Management

5.6.1 Device Settings

5.6.1.1 General

<u>Step 1</u> Select Setting > System > General > General.

The General interface is displayed. See Figure 5-135.

Figure 5-135 General settings

General	Date&Time	
Name	5C07BA7YAJ51BEB	
Language	English	
Video Standard	PAL 🗸	
	Default Refresh Save	

<u>Step 2</u> Configure parameters as needed. For parameter description, see Table 5-46.



Table 5-46 General setting parameter description	
Parameter	Description
Name	Set the device name.
	Different devices have different names.
Language	Select the language to be displayed.
Video Standard	Select video standard from PAL and NTSC.
Stop 2 Click Save	

Step 3 Click Save.

5.6.1.2 Date & Time

<u>Step 1</u> Select Setting > System > General > Date&Time.

The **Date&Time** interface is displayed. See Figure 5-136.

Figure 5-136 Date & time

General	Date& Time
Date Format	YYYY-MM-DD 🗸
Time Format	24-Hour V
Time Zone	(UTC+06:00) Astana
Current Time	2020-02-27 09 : 15 : 10 Sync PC
DST	
DST Type	Date Week
Start Time	Jan 💙 1 💙 00 : 00 : 00
End Time	Jan 💙 2 💙 00 : 00 : 00
NTP	
Server	clock.isc.org
Port	123
Interval	10 Min. (0~30)
	Default Refresh Save

<u>Step 2</u> Configure parameters as needed. See Table 5-47.

Table 5-47 Date & time parameter description

Parameter	Description
Date Format	Select the date format. Three formats are available: YYYY-MM-DD,
Date Format	MM-DD-YYYY and DD-MM-YYYY.
Time Format	Select the time format. Two formats are available: 24-Hour and 12-Hour .
Time Zone	Set the local time zone.
Current Time	The current time of the Device.
DST	Set the Start Time and End Time of DST in the Date format or Week
	format.



Parameter	Description
NTP	Select the NTP check box to enable the network time sync function.
Server	Set the address of the time server.
	Set the network timing function of NTP server, and the Device time will be
	synchronized with the server time.
Port	Set the port number of the time server.
Interval	Set the synchronization interval of the Device and the time server.
	Set the port number of the time server.

Step 3 Click Save.

5.6.2 Account Settings

5.6.2.1 Account

User management is only available for admin users.

- For **Username** and **Group Name**, the maximum length is 15 characters. Username can only consist of numbers, letters, underlines, dots and @; group name can only consist of numbers, letters and underlines.
- The password should consist of 8 to 32 non-blank characters and contain at least two types of characters among upper case, lower case, number, and special characters (excluding ' "; : &). The confirming password shall be the same as the new password. Set a high security password according to the prompt of password strength.
- The number of users and groups is 19 and 8 respectively by default.
- User management adopts a two-level method of group and user. Neither group names nor user names can be duplicated, and a user can only belong to one group.
- Users currently logged in cannot modify their own permissions.
- The user is admin by default. The **admin** account is defined as high privileged user.

5.6.2.1.1 Username

Select **Setting > System > Account > Account > Username**, and you can enable anonymous login, add users, delete users, modify user passwords, and perform other operations. For the configuration interface, see Figure 5-137.

Username	Group Name		-					
No.	Username	- A CARLER	Name	Memo	_	Restricted Login	Modify	Delete
1	admin	adi	min	admin 's accour		1	1	•
Authority								
	Live	Playback	System	System Info	Manual Control	File Backup	Storage	
Authority User Event	Live Network	Playback Peripheral	System AV Parameter	System Info PTZ	Manual Control Security	File Backup Maintenance	Storage	

Figure 5-137 Account interface



No permission is available for version information and other buttons except **Relay-out**, **Mark**, and **Wiper Control** in **Live** interface for the time being.

Anonymous Login

Select the **Anonymous Login** check box, and you can log in to the Device anonymously without username and password after entering IP. Anonymous users only have preview permission in the permission list. In the anonymous login, click **Logout** to log in to the Device by using other usernames.

After **Anonymous Login** is enabled, the user can view audio and video data without authentication. Think twice before enabling the function.

Adding Users

Add users in the group and set permissions.

As the default user with the highest authority, admin cannot be deleted.

Step 1 Click Add User.

The Add User interface is displayed. See Figure 5-138.



Figure 5-138 Adding users

Add User				X
Username		Must		
Password				
	The minimum pass phras	e length is 8 characte	ers	
	Weak Medium Str	ong		
Confirm Password				
Group Name	admin	~		
Memo				
Os asstina Descritacion	Destricted Legis			
Operation Permission	n Restricted Login			
All		,		^
User				
✓ Live				
Playback				
System				
System Info				
Manual Control				
File Backup				
Storage				
Event				
Network				
Peripheral				
AV Parameter				
PTZ				
Security				
Maintenance				~
		Save	Cancel	

<u>Step 2</u> Enter **Username** and **Password**, confirm password, select **Group Name**, and then add **Memo**.

<u>Step 3</u> Set Operation Permission and Restricted Login.

- Operation Permission: Click **Operation Permission**, and then select the operation permission of the user as needed.
- Restricted Login: **Click Restricted Login**, and the interface shown in Figure 5-139 is displayed. You can control login to the Device by setting the **IP Address**, **Validity Period** and **Time Range**.



Figure 5-139 Restricted login

Username Must Password
Password
The minimum pass phrase length is 8 characters Weak Medium Strong Group Name admin admin Memo Operation Permission Restricted Login IP Address 1 . 0 . 0 . 1 IPv4 IP Address IPv4 IP Address IP Address 0 8 : 00 : 00 End Time 2019-12-04 0 2 4 6 8 10 12 14 16 18 20 22 24
Weak Medium Strong Confirm Password
Confirm Password
Group Name admin Memo Operation Permission Restricted Login IP Address IP Address
Memo Operation Permission Restricted Login IP Address IP Address IP Address I . 0 . 0 . 1 IV4 IP Address IP Address 1 . 0 . 0 . 1 Validity Period Begin Time 2019-12-04 IP Address 08 : 00 : 00 End Time 2019-12-05 IP Range 0 0 2 4 6
Operation Permission Restricted Login IP Address IP Address 1 . 0 . 0 . 1 IPv4 IP Address 1 . 0 . 0 . 1 Validity Period Image 08 : 00 : 00 End Time 2019-12-05 Image 0 2 4 6 8 10 12 14 16 18 20 22 24
IP Address IP 4ddress IP 4 ✓ IP Address Validity Period Begin Time 2019-12-04 Image 0 2 4 6 8 10 12 14 16 18 20 22 24
IP Address IP 4 ✓ IP Address ✓ 1 0 0 1 Validity Period Begin Time 2019-12-04 Im 08 : 00 : 00 End Time 2019-12-05 Im 08 : 00 : 00 Time Range 0 2 4 6 8 10 12 14 16 18 20 22 24
IPv4 ✓ IP Address ✓ 1 0 0 1 Validity Period Begin Time 2019-12-04 Image 08 : 00 : 00 00 End Time 2019-12-05 Image 08 : 00 : 00 00 Time Range 0 2 4 6 8 10 12 14 16 18 20 22 24
Validity Period Begin Time 2019-12-04 Image 08 : 00 : 00 Image 0 2 4 6 8 10 12 14 16 18 20 22 24
Begin Time 2019-12-04 Im 08 : 00 : 00 End Time 2019-12-05 Im 08 : 00 : 00 Time Range 0 2 4 6 8 10 12 14 16 18 20 22 24
End Time 2019-12-05 Time Range 0 2 4 6 8 10 12 14 16 18 20 22 24
Time Range 0 2 4 6 8 10 12 14 16 18 20 22 24
0 2 4 6 8 10 12 14 16 18 20 22 24
Sun
Mon
Tue
Wed
Thu
Fri
Sat Setting
Save Cancel

- Once the group is selected as needed, the user permission can only be a subset of the group, and cannot exceed its permission attributes.
- It is recommended to give less permissions to general users than advanced users. <u>Step 4</u> Click **Save**.

Modifying Users

Step 1 Click corresponding to the user you want to modify.

The Modify User interface is displayed. See Figure 5-140.



Figure 5-140 Modifying users

Modify User				×
Username	admin	~		
Modify Password				
Group Name	admin	~		
Memo	admin 's account			
Authority	🕅 All			
	User		^	
	Live		1	
	Playback		0	
	System			

<u>Step 2</u> Modify user information as needed.

Step 3 Click Save.

Modifying Password

- <u>Step 1</u> Select the **Modify Password** check box.
- Step 2 Enter old password and new password, and confirm password.
- Step 3 Click Save.

Deleting Users

Click \bigcirc corresponding to the user to be deleted, and the user can be deleted.

Users/user groups cannot be recovered after deletion. Think twice before performing the operation.

5.6.2.1.2 Group Name

Select **Setting > System > Account > Account > Group Name**, and you can add groups, delete groups, modify group passwords, and perform other operations. For the interface, see Figure 5-141.

		and the second se									Detaile
No		Group Name				Meno.				Modify	
		admin				administrator gro	ab .				0
2		user				nizes Buonb				× .	•
Authority Iser	Live	Playback	System	System info	Manual Control	File Backup	Storage	Event	Retwork	Peripheral	

Figure 5-141 User group settings

Adding Groups

For specific operations, refer to "5.6.2.1.1 Username."

Modifying Groups

For specific operations, refer to "5.6.2.1.1 Username."

Deleting Groups

For specific operations, refer to "5.6.2.1.1 Username."

5.6.2.2 Onvif User

On the web interface, you can add ONVIF users, or modify existing users.

Step 1 Select Setting > System > Account > Onvif User.

The Onvif User interface is displayed. See Figure 5-142.

Figure 5-142 Onvif user



Step 2 Click Add User.

The Add User interface is displayed. See Figure 5-143.

Figure 5-143 Adding users

Add User		X
Username	Must	
Password		
	The minimum pass phrase length is 8 characters	
	Weak Medium Strong	
Confirm Password		
Group Name	admin 🗸	
	Save Cancel	

<u>Step 3</u> Set the username and password, confirm password, and then select the group name. <u>Step 4</u> Click **Save**.



- Click local to modify user information.



5.6.3 Safety

5.6.3.1 RTSP Authentication

Set the authentication method for media stream.

<u>Step 1</u> Select Setting > System > Safety > RTSP Authentication.

The **RSTP Authentication** interface is displayed. See Figure 5-144.

Figure 5-144 RTSP authentication

RTSP Authentication	System Service	HTTPS	Firewall
Authorize Mode	Digest	~	
Default	Refresh	Save	

<u>Step 2</u> Select the **Authorize Mode**. You can select from **Digest**, **Basic** and **None**. It is **Digest** by default.

- Click Default, and Digest is selected automatically.
- Select **None**, and "Non-authentication mode may have risk. Are you sure to enable it" prompt will be displayed. Think twice before selecting the mode.
- Select **Basic** mode, and "Basic authentication mode may have risk. Are you sure to enable it?" prompt will be displayed. Think twice before selecting the mode.

5.6.3.2 System Service

You can configure system service to ensure system security.

<u>Step 1</u> Select Setting > System > Safety > System Service. The System Service interface is displayed. See Figure 5-145.



Figure 5-145 System service

RTSP A	uthentication S	ystem Service	HTTPS	Firewall		
	SSH	Enable				
	Multicast/Broadcas	t 🗹 Enable				
	Password Reset	Enable	Email Address]	
	CGI Service	Enable				
	Onvif Service	Enable				
	Genetec Service	Enable				
	Audio and Video Tr	r 📃 Enable	*Please make su	ire matched device or softwar	e supports video decryption fun	ction.
	Mobile Push	Enable				
	Private Protocol Au	t Security Mode (Recomi 🗸			
	Default	Refresh	Save			

<u>Step 2</u> Configure system service parameters. For the detailed description, see Table 5-48.

Function	Description
	You can enable SSH authentication to perform safety management.
	The function is disabled by default.
SSH	
	It is recommended to disable SSH. If this function is enabled, there
	might be security risks.
	Enable this function, and when multiple users are viewing the
	monitoring screen simultaneously through network, they can find the
Multicast/Broadcast	Device through multicast/broadcast protocol.
Search	
	It is recommended to disable the multicast/broadcast search function.
	If this function is enabled, there might be security risks.
	You can enable Password Reset to perform security management.
	The function is enabled by default.
Password Reset	
Fassword Nesel	If the function is disabled, you can only reset the password after restoring
	the Device to factory defaults through pressing the Reset button on the
	device.
	You can access the Device through this protocol. The function is
	enabled by default.
CGI Service	
	It is recommended to disable the function. If this function is enabled,
	there might be security risks.
	You can access the Device through this protocol. The function is
Onvif Service	enabled by default.

Table 5-48 System service parameter description



Function	Description
	It is recommended to disable the function. If this function is enabled,
	there might be security risks.
Audio and Video Transmission Encryption	 Enable this function to encrypt the stream transmitted through the private protocol. Make sure that the matched devices or software support video decryption function. It is recommended to enable the function. If the function is disabled, there might be risk of data leakage.
Mobile Push	 Push the alarm snapshot triggered by the Device to the mobile phone. The function is enabled by default. It is recommended to disable the function. If this function is enabled, there might be security risks.
Private Protocol	You can select Security Mode and Compatible Mode . Security mode
Authentication	is recommended. If you select compatibility mode, there might be
Mode	security risks.

Step 3 Click Save.

5.6.3.3 HTTPS

It is recommended to enable HTTPS service. If the service is disabled, there might be risk of data leakage.

Create certificate or upload signed certificate, and then you can log in through HTTPS with your PC. HTTPS can ensure data security, and protect user information and device security with reliable and stable technology.

<u>Step 1</u> Create certificate or upload the signed certificate.

- If you select **Create Certificate**, refer to the following steps.
 - 1) Select Setting > System > Safety > HTTPS.

The HTTPS interface is displayed. See Figure 5-146.



Figure 5-146 HTTPS (1)										
RTSP Authentication Sy	stem Service	HTTPS	Firewall							
Enable HTTPS	_									
Protocol Version										
Enable TLSv1.0										
Create Certificate										
Create										
Request Created										
Request Created				Delete	Install	Download				
Install Signed Certific	ate									
Certificate Path				Browse						
Certificate Key Path				Browse	Upload					
Certificate Installed										
Certificate Installed				Delete						
Attribute										
	Refresh	Save]							

2) Click Create.

The **HTTPS** dialog box is displayed. See Figure 5-147. Figure 5-147 HTTPS (2)

HTTPS		
Region	[*e.g. CN
IP or Domain name		*
Validity Period	365	Day*Range 1-5000
Province	none	
Location	none	
Organization	none	
Organization Unit	none	
Email	5	
[Create	Cancel
3) Enter the requi	red information, and then cli	ick Create .

- The entered IP or domain name must be the same as the IP or domain name of the Device.
- 4) Click **Install** to install the certificate on the Device. See Figure 5-148.



	Figure	e 5-148 Ce	rtificate instal	lation		
RTSP Authentication Sy	stem Service	HTTPS	Firewall			
Enable HTTPS						
Protocol Version						
Enable TLSv1.0						
Create Certificate						
Create						
Request Created						
Request Created	Manager and a s		Second (Second)	Delete	Install	Download
Install Signed Certific	ate					
Certificate Path				Browse		
Certificate Key Path				Browse,	Upload	
Certificate Installed						
Certificate Installed	(FE 16 18 1	1.111103.5	l teal are 3	Delete		
Attribute	lanaa in 1000-1000 Lanaa in 1000-1000 Lanaa in 1000-1000	140-14-18-1031-0 1				
	Refresh	Save				

Click Download to download root certificate.
 The Save As dialog box is displayed. See Figure 5-149.
 Figure 5-149 Downloading root certificate

🥖 Save As	×
🕒 🗢 🧊 🕨 Libraries 🕨	 ✓ ✓ Search Libraries
Organize 🕶	
E Desktop Downloads E Recent Places	Deen a library to see your files and arrange them by folder,
▲ □ Libraries	Documents Library
Documents	~
🖻 🎝 Music	Music
Pictures	Library
Videos	Pictures Library
🔺 🕎 Computer	Clotary
🖻 🏭 Local Disk (C:)	Videos
🖻 🧫 DISK1_VOL2 (D:)	Library
DISK1_VOL3 (E:)	*
File name: RootCert.cer	÷
Save as type: (*.cer)	*
Hide Folders	Save Cancel

- 6) Select storage path, and then click **Save**.
- 7) Double-click the **RootCert.cer** icon.
 - The Certificate interface is displayed. See Figure 5-150.



Figure 5-150 Certificate information

Thi	Certificate Information
ins	tall this certificate in the Trusted Root Certification the thorities store.
	Issued to: test
	Issued by: test
	Valid from 2016/ 7/ 8 to 2020/ 7/ 7

8) Click Install Certificate.

The Certificate Import Wizard interface is displayed. See Figure 5-151.



Figure 5-151 Certificate import wizard



9) Click Next.

Select Trusted Root Certification Authorities. See Figure 5-152.



Figure 5-152 Certificate storage area

Certificate Store		
Certificate stores are sy	ystem areas where certificate	es are kept.
Windows can automatic the certificate.	ally select a certificate store,	, or you can specify a location fo
Automatically selected	ect the certificate store based	d on the type of certificate
Place all certificat	tes in the following store	
Certificate store		
Trusted Root Ce	ertification Authorities	Browse
.earn more about <u>certificate</u>	stores	
	< Ba	ack Next > Ca
	< Da	INEXT >

10) Click Next.

The **Completing the Certificate Import Wizard** interface is displayed, see Figure 5-153.



Figure 5-153 Completing the certificate import wizard




- 11) Click Finish.
 - The Security Warning dialog box is displayed. See Figure 5-154.









12) Click Yes.

The import was successful dialog box is displayed. Click OK to complete the certificate installation. See Figure 5-155.

Figure 5-155 Import success



- If you select Install Signed Certificate, refer to the following steps.
- 1) Select Setting > System > Safety > HTTPS. The HTTPS interface is displayed. See Figure 5-156.



Figure 5-156 Install signed certificate

RTSP Authentication System	Service HTTPS	Firewall			
Enable HTTPS					
Protocol Version					
Enable TLSv1.0					
Create Certificate					
Create					
Request Created					
Request Created			Delete,	install	Download
Install Signed Certificate					
Certificate Path	(income)		Browse		
Certificate Key Path	in the second se		Browse	Up)oad	
Certificate Installed					
Certificate Installed			Delete		
Attribute					
_		ì.			
	Refresh Save				

- Click Browse to upload the signed certificate and certificate key, and then click Upload.
- 3) To install the root certificate, refer to Step 5) to 12) in **Create Certificate**.

Step 2 Select Enable HTTPS and click Save.

The **Reboot** interface is displayed, and the configuration takes effect after reboot. See Figure 5-157.

Figure 5-157 Reboot

Rebo	pot
4	The configuration takes effect, the device is restarting now, please don't leave this page or close the browser
	Enter https://xx.xx.xx.xx in the browser to open the login interface. If no certificate i

Enter <u>https://xx.xx.xx</u> in the browser to open the login interface. If no certificate is installed, a certificate error prompt will be displayed.

- If HTTPS is enabled, you cannot access the Device through HTTP. The system will switch to HTTPS if you access the Device through HTTP.
- The deletion of created and installed certificates cannot be restored. Think twice before deleting them.

5.6.3.4 Firewall

Set a firewall for the Device to prevent network attacks after the Device is connected to the network.

<u>Step 1</u> Select Setting > System > Safety > Firewall.

The Firewall interface is displayed. See Figure 5-158.



Figure 5-158 Firewall

RTSP Authentication	System Service	HTTPS	Firewall	
Rule Type	Network Acces	s 🗸		
Enable				
Default	Refresh	Save		

<u>Step 2</u> Select the type of network attack that the firewall resists as needed. You can select **Network Access**, **PING Prohibited**, or **Prevent Semijoin**.

Step 3 Select Enable, and then the Firewall is enabled.

Step 4 Click Save.

5.6.4 Peripheral

The peripheral functions might vary with different models, and the actual interface shall prevail.

5.6.4.1 Wiper

<u>Step 1</u> Select Setting > System > Peripheral > Wiper.

The **Wiper** interface is displayed. See Figure 5-159.

Figure 5-159 Wiper settings

Wiper	
Mada	Manual
Mode	Manual
Interval Time	10 s (0~255)
✓ Working Duration	on 10 Min. (10~1440)
	Default Refresh Save

Step 2 Configure parameters as needed. For parameter description, see Table 5-49.

Parameter	Description
Mode	Set the wiper mode. It is Manual by default.
Mode	In Manual mode, you need to manually start the wiper.
Interval Time	The time between wiper starting to wiper ending.
Working	Set the maximum duration of the wiper operating once in Manual mode.
Duration	The value ranges from 10 minutes to 1440 minutes.

Table 5-49 Wiper setting parameter description

Step 3 Click Save.



5.6.5 Default



All information except IP address and user management will be restored to defaults. Think twice before performing the operation.

Select **Setting > System > Default**, and click **Default** to restore the Device. The configuration interface is displayed. See Figure 5-160.

Figure 5-160 Default interface

Default	
Default	Other configurations will be recovered to default except network IP address, user management and so on.
Factory Default	Completely recover device parameters to factory default.

Select the recovery mode as needed.

- Default: All information except IP address and user management will be restored to defaults.
- Factory Default: The function is equivalent to the Reset button of the Device. All configuration information of the Device can be restored to the factory defaults, and the IP address can also be restored to the original IP address. After clicking **Factory Default**, you need to enter the password of admin user on the interface displayed. The Device can be restored to factory defaults only after the system confirms that the password is correct.

 \square

- Only admin user can use this function.
- When the Device is restored to factory defaults, all information except the data in the external storage media will be erased. Delete data in external storage media by formatting and other methods.

5.6.6 Import/Export

When multiple devices share the same configuration methods, they can be quickly configured by importing and exporting configuration files.

<u>Step 1</u> On the web interface of one device, select **Setting > System > Import/Export**. The **Import/Export** interface is displayed. See Figure 5-161.



Figure 5-161 Import/Export

Import/Export		
Backup Path		
Import	Export	

<u>Step 2</u> Click **Export** to export the configuration file (.backup file) to the local storage path.

<u>Step 3</u> Click **Import** on the **Import/Export** interface of the Device to be configured to import the configuration file, and the Device will complete the configurations.

5.6.7 Auto Maintain

You can select Auto Reboot or Auto Delete Old Files.

- If you select Auto Reboot, the frequency and time need to be set.
- If you select **Auto Delete Old Files**, you need to set the time period for the files to be deleted.

<u>Step 1</u> Select Setting > System > Auto Maintain.

The Auto Maintain interface is displayed. See Figure 5-162.

Figure 5-162 Auto maintain

Auto Maintain	
Auto Reboot	
Auto Delete Old Files	
Manual Reboot	
Refresh Save	

<u>Step 2</u> Configure parameters as needed. For parameter description, see Table 5-50.

Parameter	Description	
Auto Reboot	Select the check box to set the Device reboot time.	
	Select the check box to customize the time period for the files to be deleted.	
	The value ranges from 1 day to 31 days.	
Auto Delete Old Files	\triangle	
1 1100	When you enable the function, The deleted files cannot be recovered.	
	Are you sure to enable this function now? prompt will be displayed.	
	Think twice before enabling the function.	

Table 5-50 Auto maintain parameter description

<u>Step 3</u> Click **Save** and the configuration will take effect.



5.6.8 Upgrade

Upgrade the system to improve device function and stability.

If wrong upgrade file has been used, restart the Device; otherwise some functions might not work properly.

Select **Setting > System > Upgrade**. The configuration interface is displayed. See Figure 5-163.

Figure 5-163 System upgrade

elect Firmware File		Browse	Upgrade
ine Upgrade			
Auto-check for updates	Save		
Auto-check for updates System Version	Save		Manual Check

- File Upgrade: Click **Browse**, select the upgrade file, and then click **Upgrade** to upgrade the firmware. The upgrade file is in the format of *.bin.
- Online Upgrade
 - 1) Select the Auto-check for updates check box.

This will enable the system to check for upgrade once a day automatically, and there will be system notice if any upgrade is available.

We need to collect the data such as IP address, device name, firmware version, and device serial number to perform auto-check. The collected information is only used to verify the legitimacy of the Device, and push the upgrade notification.

- 2) Click Save.

Click Manual Check, and you can check for upgrade manually.

5.7 Information

You can view information such as version, online users, log, and life statistics.

5.7.1 Version

You can view information such as system hardware features, software version and release date.



Select **Setting > Information > Version > Version**, and then you can see the version information of current web interface. See Figure 5-164.

Figure 5-164 Version

Version	
Device Type	EVEL REPORT OF LEAST AVEC
System Version	VERSION AND A REPORT OF A MILLION AND AND A MILLION AND AND AND AND AND AND AND AND AND AN
WEB Version	100.000
ONVIF Version	101200-000000
PTZ Version	CAR MERCE & REAL (MARK) (2000
S/N	CONTRACTOR NO.
Security Baseline V	12.2
Copyright 2019, all righ	its reserved.

5.7.2 Log Information

5.7.2.1 Log

Select **Setting > Information > Log > Log**, and then you can see the operation information of the Device, and some system information. See Figure 5-165. For parameter description, see Table 5-51.

Figure 5-165 Log

Log	Remote Log					
Start Time	2019-12-03	T 09	41 19 End Time	2019-12-04 🛅 09 41 19		
Туре	All	~	Search			
No.			Log Time	the second s	Disername	Log Type
Detailed Informa						
Time:	woo.					
Usemame						
Туре:						
Content						
						(4 4 1/1 + b) 1 (<u>4</u>)
Backup						Clear



Parameter	Description	
Start Time	The start time of the log to be searched (January 1, 2000 is the earliest	
	time).	
End Time	The end time of the log to be searched (December 31, 2037 is the latest	
	time).	
Туре	The log type includes All, System, Setting, Data, Event, Record, Account,	
туре	Clear Log, and Safety.	
	Set the start time and end time of the log to be searched, select the log	
Search	type, and then click Search . The searched log number and time period will	
	be displayed.	
Detailed	Click a log to display the details.	
Information	Click a log to display the details.	
Clear	Clear all logs of the Device, and classified clearing is not supported.	
	Back up the searched system logs to the PC currently used by the user.	
Pookup		
Backup	The data will be overwritten if the disk is full. Back up the data in time as	
	needed.	

Table 5-51 Log parameter description

Here are the meanings of different log types:

- **System**: Includes program launch, force exit, exit, program reboot, device shutdown/restart, system reboot, and system upgrade.
- Setting: Includes saving configurations, and deleting configuration files.
- **Data**: Includes disk type configurations, data erasing, hot swap, FTP state, and recording mode.
- **Event** (records events such as video detection, smart plan, alarm, and abnormality): Includes starting events, and ending events.
- **Record**: Includes file access, file access error, and file search.
- Account (records modification of user management, login, and logout): Includes login, logout, adding user, deleting user, modifying user, adding group, deleting group, and modifying group.
- **Safety**: Includes security-related information.
- **Clear Log**: Clearing logs.

5.7.2.2 Remote Log

Upload the Device operations to the log server.

<u>Step 1</u> Select Setting > Information > Log > Remote Log.

The **Remote Log** interface is displayed. See Figure 5-166.



Figure 5-166 Remote log

Log Rer	note Log
Enable	
IP Address	192. 168. 0. 108
Port	514 (1~65534)
Device Number	22 (0~23)
	Default Refresh Save

- <u>Step 2</u> Select **Enable**, and then remote log function is enabled.
- Step 3 Set the IP Address, Port and Device Number of the log server.

Click Default to restore the Device to the default settings.

5.7.3 Online User

Select **Setting > Information > Online User**, and the **Online User** interface is displayed. See Figure 5-167.

Figure 5-167 Online users

No:	Lisemame	User Lacel Group	IFI Address	User Loop Time
1	admin.	admin	194994	User Lopin Time
in				



6 Alarm

You can select alarm types on the interface. When the selected alarms are triggered, detailed alarm information will be displayed on the right side of the interface. You can also select **Prompt** or **Play Alarm Tone**. When an alarm occurs, the alarm prompt or tone will be triggered. For the **Alarm** setting interface, see Figure 6-1. For parameter description, see Table 6-1.

Figure 6-1	Alarm setting	interface
------------	---------------	-----------

Alarm Type	Na	Tinta	Alarm Type	Source IP	Alarm Channel
Motion Detection Disk Full Disk Full Disk Fur Disk Score Charging Prompt New Tone					
Play Alarm Tone	<u></u>				

Category	Parameter	Description
	Motion Detection	Record alarm information in case of motion detection.
	Disk Full	Record alarm information in case of full disk.
	Disk Error	Record alarm information in case of disk error.
	Video Tamper	Record alarm information in case of video tampering.
Alarm	External Alarm	Record alarm information in case of an external alarm.
Туре	Illegal Access	Record alarm information in case of illegal access.
	Audio Detection	Record alarm information in case of audio detection.
	IVS	Record alarm information in case of smart events.
	Scene Changing	Record alarm information in case of scene changing.
	Security Exception	Record alarm information in case of security exception.
Operation	Prompt	Select the Prompt check box. When you are not on the Alarm interface, and the selected alarm event is triggered, the Relay-out button on the main menu will change to , and the alarm information will be automatically recorded. After you click the Alarm menu bar, the button disappears.
Alarm Tone	Play Alarm Tone	Select the check box, and then select the tone file path. When the selected alarm event is triggered, the selected tone file will be played to prompt you that an alarm event

Table 6-1 Alarm setting parameter description



Category	Parameter	Description
		is triggered.
	Tone Path	Customize the storage path for alarm tones.



7 Logout

Click **Logout** to log out, and the login interface is displayed. See Figure 7-1. Enter the username and password to log in again.

Figure 7-1 Login interface

IP PTZ Camera		
Username: Password:	admin	Forgot password?
	Login Cancel]



Appendix 1 Cybersecurity Recommendations

Cybersecurity is more than just a buzzword: it's something that pertains to every device that is connected to the internet. IP video surveillance is not immune to cyber risks, but taking basic steps toward protecting and strengthening networks and networked appliances will make them less susceptible to attacks. Below are some tips and recommendations from Dahua on how to create a more secured security system.

Mandatory actions to be taken for basic equipment network security:

1. Use Strong Passwords

Please refer to the following suggestions to set passwords:

- The length should not be less than 8 characters;
- Include at least two types of characters; character types include upper and lower case letters, numbers and symbols;
- Do not contain the account name or the account name in reverse order;
- Do not use continuous characters, such as 123, abc, etc.;
- Do not use overlapped characters, such as 111, aaa, etc.;

2. Update Firmware and Client Software in Time

- According to the standard procedure in Tech-industry, we recommend to keep your equipment (such as NVR, DVR, IP camera, etc.) firmware up-to-date to ensure the system is equipped with the latest security patches and fixes. When the equipment is connected to the public network, it is recommended to enable the "auto-check for updates" function to obtain timely information of firmware updates released by the manufacturer.
- We suggest that you download and use the latest version of client software.

"Nice to have" recommendations to improve your equipment network security:

1. Physical Protection

We suggest that you perform physical protection to equipment, especially storage devices. For example, place the equipment in a special computer room and cabinet, and implement well-done access control permission and key management to prevent unauthorized personnel from carrying out physical contacts such as damaging hardware, unauthorized connection of removable equipment (such as USB flash disk, serial port), etc.

2. Change Passwords Regularly

We suggest that you change passwords regularly to reduce the risk of being guessed or cracked.

3. Set and Update Passwords Reset Information Timely

The equipment supports password reset function. Please set up related information for password reset in time, including the end user's mailbox and password protection questions. If the information changes, please modify it in time. When setting password protection questions, it is suggested not to use those that can be easily guessed.

4. Enable Account Lock

The account lock feature is enabled by default, and we recommend you to keep it on to guarantee the account security. If an attacker attempts to log in with the wrong password several times, the corresponding account and the source IP address will be locked.



5. Change Default HTTP and Other Service Ports

We suggest you to change default HTTP and other service ports into any set of numbers between 1024~65535, reducing the risk of outsiders being able to guess which ports you are using.

6. Enable HTTPS

We suggest you to enable HTTPS, so that you visit Web service through a secure communication channel.

7. Enable Whitelist

We suggest you to enable whitelist function to prevent everyone, except those with specified IP addresses, from accessing the system. Therefore, please be sure to add your computer's IP address and the accompanying equipment's IP address to the whitelist.

8. MAC Address Binding

We recommend you to bind the IP and MAC address of the gateway to the equipment, thus reducing the risk of ARP spoofing.

9. Assign Accounts and Privileges Reasonably

According to business and management requirements, reasonably add users and assign a minimum set of permissions to them.

10. Disable Unnecessary Services and Choose Secure Modes

If not needed, it is recommended to turn off some services such as SNMP, SMTP, UPnP, etc., to reduce risks.

If necessary, it is highly recommended that you use safe modes, including but not limited to the following services:

- SNMP: Choose SNMP v3, and set up strong encryption passwords and authentication passwords.
- SMTP: Choose TLS to access mailbox server.
- FTP: Choose SFTP, and set up strong passwords.
- AP hotspot: Choose WPA2-PSK encryption mode, and set up strong passwords.

11. Audio and Video Encrypted Transmission

If your audio and video data contents are very important or sensitive, we recommend that you use encrypted transmission function, to reduce the risk of audio and video data being stolen during transmission.

Reminder: encrypted transmission will cause some loss in transmission efficiency.

12. Secure Auditing

- Check online users: we suggest that you check online users regularly to see if the device is logged in without authorization.
- Check equipment log: By viewing the logs, you can know the IP addresses that were used to log in to your devices and their key operations.

13. Network Log

Due to the limited storage capacity of the equipment, the stored log is limited. If you need to save the log for a long time, it is recommended that you enable the network log function to ensure that the critical logs are synchronized to the network log server for tracing.

14. Construct a Safe Network Environment

In order to better ensure the safety of equipment and reduce potential cyber risks, we recommend:

• Disable the port mapping function of the router to avoid direct access to the intranet devices from external network.



- The network should be partitioned and isolated according to the actual network needs. If there are no communication requirements between two sub networks, it is suggested to use VLAN, network GAP and other technologies to partition the network, so as to achieve the network isolation effect.
- Establish the 802.1x access authentication system to reduce the risk of unauthorized access to private networks.

ENABLING A SAFER SOCIETY AND SMARTER LIVING

Zhejiang Dahua Vision Technology Co., Ltd | Address: No.1199 Bin an Road, Binjiang District, Hangzhou, PRC. | Tel: +86-571-87688883 Website: www.dahuasecurity.com | Fax: +86-571-87688815 | Email: overseas@dahuatech.com | Postcode: 310053